

**Image Management Service** 

## **API Reference**

Date 2023-02-13

## **Contents**

1 Before You Start	1
1.1 Overview	1
1.2 API Calling	1
1.3 Endpoints	1
1.4 Constraints	1
1.5 Concepts	2
1.6 Selecting an API Type	3
2 API Overview	4
3 Calling APIs	5
3.1 Making an API Request	5
3.2 Authentication	
3.3 Response	10
4 Getting Started	12
5 IMS APIs	14
5.1 Image	14
5.1.1 Querying Images	14
5.1.2 Updating Image Information	28
5.1.3 Creating an Image	37
5.1.4 Importing an Image File Quickly	49
5.1.5 Creating a Data Disk Image Using an External Image File	55
5.1.6 Creating a Full-ECS Image	58
5.1.7 Registering an Image	63
5.1.8 Exporting an Image	65
5.1.9 Querying Supported Image OSs	67
5.2 Image Sharing	70
5.2.1 Deleting Image Members in Batches	70
5.2.2 Adding Image Members in Batches	71
5.2.3 Updating the Status of Image Members in Batches	73
5.3 Image Replication	
5.3.1 Replicating an Image Within a Region	75
5.3.2 Replicating an Image Across Regions	
5.4 Image Quota	80

5.4.1 Querying the Image Quota	
5.5 Image Jobs	
5.5.1 Asynchronous Job Query	82
6 Native OpenStack APIs	87
6.1 Image (Native OpenStack APIs)	87
6.1.1 Querying Images (Native OpenStack API)	87
6.1.2 Querying Image Details (Native OpenStack API)	103
6.1.3 Updating Image Information (Native OpenStack API)	111
6.1.4 Uploading an Image (Native OpenStack API)	122
6.1.5 Deleting an Image (Native OpenStack API)	124
6.1.6 Creating Image Metadata (Native OpenStack API)	126
6.1.7 Deleting an Image (Native OpenStack API v1.1 - Abandoned and Not Recommended)	133
6.1.8 Querying Image Metadata (Native OpenStack API v1 - Abandoned and Not Recommended)	134
6.1.9 Querying Image Details (Native OpenStack API v1.1 - Abandoned and Not Recommended)	137
6.2 Image Schema (Native OpenStack APIs)	139
6.2.1 Querying an Image Schema (Native OpenStack API)	139
6.2.2 Querying an Image List Schema (Native OpenStack API)	144
6.2.3 Querying an Image Member Schema (Native OpenStack API)	149
6.2.4 Querying an Image Member List Schema (Native OpenStack API)	150
6.3 Image Sharing (Native OpenStack APIs)	152
6.3.1 Adding an Image Member (Native OpenStack API)	152
6.3.2 Updating the Image Sharing Status in Batches (Native OpenStack API)	154
6.3.3 Querying Image Member Details (Native OpenStack API)	156
6.3.4 Querying Image Members (Native OpenStack API)	158
6.3.5 Deleting an Image Member (Native OpenStack API)	160
6.4 API Version Query (Native OpenStack API)	161
6.4.1 Querying API Versions (Native OpenStack API)	161
6.4.2 Querying an API Version (Native OpenStack API)	163
7 Examples	166
7.1 Creating an Image from an ISO File	
8 Permission Policies and Supported Actions	
8.1 Introduction	
8.2 Image Management	
8.3 Image Schema	
8.4 Image Sharing	
8.5 Image Replication	
8.6 Image Quota	
9 Common Parameters	
9.1 Image Attributes	
9.2 Image Tag Data Formats	
9.3 Restrictions on Image Sharing	I Ö Š

Image	Management	Service

API Reference	Contents
9.4 Obtaining a Project ID	183
9.5 Values of Related Parameters	185
A Status Codes	193
B Error Codes	195
C Change History	215

2023-02-13 iv

# Before You Start

#### 1.1 Overview

Welcome to *Image Management Service API Reference*. An image is a template used to create a server or disk. Image Management Service (IMS) provides image lifecycle management. You can use a server or an external image file to create a system or data disk image, or use an Elastic Cloud Server (ECS) or Cloud Backup and Recovery (CBR) backup to create a full-ECS image.

This document describes how to use application programming interfaces (APIs) to perform operations on images, such as creating, querying, deleting and updating images. For details about all supported operations, see **API Overview**.

If you plan to access IMS through an API, ensure that you are familiar with IMS concepts. For details, see section "Overview" in *Image Management Service User Guide*.

## 1.2 API Calling

IMS supports Representational State Transfer (REST) APIs, allowing you to call APIs using HTTPS. For details about API calling, see Calling APIs.

## 1.3 Endpoints

An endpoint is the **request address** for calling an API. Endpoints vary depending on services and regions. For the endpoints of all services, see **Regions and Endpoints**.

## 1.4 Constraints

- The number of images that you can create is determined by your quota. To view or increase the quota, see section "How Do I Increase the Image Quota?" in *Image Management Service User Guide*.
- For more constraints, see API description.

## 1.5 Concepts

#### Account

An account is created upon successful registration. The account has full access permissions for all of its cloud services and resources. It can be used to reset user passwords and grant user permissions. The account is a payment entity, which should not be used directly to perform routine management. For security purposes, create Identity and Access Management (IAM) users and grant them permissions for routine management.

#### User

An IAM user is created by an account in IAM to use cloud services. Each IAM user has its own identity credentials (password and access keys).

API authentication requires information such as the account name, username, and password.

#### Region

A region is a geographic area in which cloud resources are deployed. Availability zones (AZs) in the same region can communicate with each other over an intranet, while AZs in different regions are isolated from each other. Deploying cloud resources in different regions can better suit certain user requirements or comply with local laws or regulations.


#### AZ

An AZ comprises of one or more physical data centers equipped with independent ventilation, fire, water, and electricity facilities. Computing, network, storage, and other resources in an AZ are logically divided into multiple clusters. AZs within a region are interconnected using high-speed optical fibers to allow you to build cross-AZ high-availability systems.

#### Project

A project corresponds to a region. Default projects are defined to group and physically isolate resources (including computing, storage, and network resources) across regions. Users can be granted permissions in a default project to access all resources under their accounts in the region associated with the project. If you need more refined access control, create subprojects under a default project and create resources in subprojects. Then you can assign users the permissions required to access only the resources in the specific subprojects.

Figure 1-1 Project isolation model



## 1.6 Selecting an API Type

The following APIs have been abandoned and are not recommended:

- Deleting an Image (Native OpenStack API v1.1 Abandoned and Not Recommended)
- Querying Image Metadata (Native OpenStack API v1 Abandoned and Not Recommended)
- Querying Image Details (Native OpenStack API v1.1 Abandoned and Not Recommended)

## **2** API Overview

IMS APIs include native OpenStack APIs and extension APIs.

A combination of the two types of APIs allows you to use all functions provided by IMS. For example, you can use either native OpenStack APIs or extension APIs to create private images.

Table 2-1 API description

Туре	Subtype	Description
IMS APIs	Image	Create, query, and export images.
	lmage sharing	Share private images with other tenants.
	Image replication	Replicate an existing image as another one. When replicating an image, you can change the image attributes to meet the requirements of different scenarios.
	Image quota	Query the number of private images in the current region.
	Image jobs	Query the execution status of an asynchronous job.
Native Image		Create, query, and export images.
OpenStack API	Image schema	An image schema is used to display details of an images or image entity, such as the entity's attributes and their data types. With an image schema, you can understand basic information about an image.
	lmage sharing	Share private images with other tenants.

# 3 Calling APIs

## 3.1 Making an API Request

This section describes the structure of a REST API request, and uses the IAM API for obtaining a user token as an example to demonstrate how to call an API. The obtained token can then be used to authenticate the calling of other APIs.

#### **Request URI**

A request URI is in the following format:

#### {URI-scheme}://{Endpoint}/{resource-path}?{query-string}

Although a request URI is included in the request header, most programming languages or frameworks require the request URI to be transmitted separately.

Table 3-1 URI parameter description

Parameter	Description
URI-scheme	Protocol used to transmit requests. All APIs use HTTPS.
Endpoint	Domain name or IP address of the server bearing the REST service. The endpoint varies between services in different regions. It can be obtained from <b>Regions and Endpoints</b> .  For example, the endpoint of IAM in the <b>ru-moscow-1</b> region is <b>iam.ru-moscow-1.hc.sbercloud.ru</b> .
resource-path	Access path of an API for performing a specified operation. Obtain the path from the URI of an API. For example, the resource-path of the API used to obtain a user token is /v3/auth/tokens.

Parameter	Description
query-string	Query parameter, which is optional. Ensure that a question mark (?) is included before each query parameter that is in the format of <i>Parameter name=Parameter value</i> . For example, ? limit=10 indicates that a maximum of 10 data records will be displayed.

#### □ NOTE

To simplify the URI display in this document, each API is provided only with a **resource-path** and a request method. The **URI-scheme** of all APIs is **HTTPS**, and the endpoints of all APIs in the same region are identical.

#### **Request Methods**

The HTTP protocol defines the following request methods that can be used to send a request to the server.

Table 3-2 HTTP methods

Method	Description	
GET	Requests the server to return specified resources.	
PUT	Requests the server to update specified resources.	
POST	Requests the server to add resources or perform special operations.	
DELETE	Requests the server to delete specified resources, for example, an object.	
HEAD	Same as GET except that the server must return only the response header.	
PATCH	Requests the server to update partial content of a specified resource.	
	If the resource does not exist, a new resource will be created.	

For example, in the case of the API used to obtain a user token, the request method is **POST**. The request is as follows:

POST https://iam.ru-moscow-1.hc.sbercloud.ru/v3/auth/tokens

#### **Request Header**

You can also add additional header fields to a request, such as the fields required by a specified URI or HTTP method. For example, to request for the authentication information, add **Content-Type**, which specifies the request body type.

Common request header fields are as follows.

Table 3-3 Common request header fields

Parameter	Description	Mandatory	Example Value
Host	Specifies the server domain name and port number of the resources being requested. The value can be obtained from the URL of the service API. The value is in the format of Hostname:Port number. If the port number is not specified, the default port is used. The default port number for https is 443.	No This field is mandatory for AK/SK authentication.	code.test.com or code.test.com: 443
Content-Type	Specifies the type (or format) of the message body. The default value application/json is recommended. Other values of this field will be provided for specific APIs if any.	Yes	application/json
Content- Length	Specifies the length of the request body. The unit is byte.	No	3495
X-Project-Id	Specifies the project ID. Obtain the project ID by following the instructions in Obtaining a Project ID.	No	e9993fc787d94b 6c886cbaa340f9c 0f4
X-Auth-Token	Specifies the user token. It is a response to the API for obtaining a user token (This is the only API that does not require authentication). After the request is processed, the value of <b>X-Subject-Token</b> in the response header is the token value.	No This field is mandatory for token authentication.	The following is part of an example token: MIIPAgYJKoZIhvc NAQcCoggg1B BIINPXsidG9rZ

#### □ NOTE

In addition to supporting authentication using tokens, APIs support authentication using AK/SK, which uses SDKs to sign a request. During the signature, the **Authorization** (signature authentication) and **X-Sdk-Date** (time when a request is sent) headers are automatically added in the request.

For more details, see "Authentication Using AK/SK" in Authentication.

The API used to obtain a user token does not require authentication. Therefore, only the **Content-Type** field needs to be added to requests for calling the API. An example of such requests is as follows:

POST https://iam.ru-moscow-1.hc.sbercloud.ru/v3/auth/tokens Content-Type: application/json

#### (Optional) Request Body

This part is optional. The body of a request is often sent in a structured format as specified in the **Content-Type** header field. The request body transfers content except the request header.

The request body varies between APIs. Some APIs do not require the request body, such as the APIs requested using the GET and DELETE methods.

In the case of the API used to obtain a user token, the request parameters and parameter description can be obtained from the API request. The following provides an example request with a body included. Replace *username*, *domainname*, \*\*\*\*\*\*\*\*\*\*\* (login password), and \*\*xxxxxxxxxxxxxxx\*\* (project name) with the actual values. Obtain a project name from \*Regions and Endpoints\*.

#### □ NOTE

The **scope** parameter specifies where a token takes effect. You can set **scope** to an account or a project under an account. In the following example, the token takes effect only for the resources in a specified project. For more information about this API, see "Obtaining a User Token".

```
POST https://iam.ru-moscow-1.hc.sbercloud.ru/v3/auth/tokens
Content-Type: application/json
  "auth": {
     "identity": {
        "methods": [
           "password"
        "password": {
           "user": {
             "name": "username",
              "password": " *******
             "domain": {
                "name": "domainname"
          }
        }
      'scope": {
        "project": {
           "name": "xxxxxxxxxxxxxxxxxx"
  }
```

If all data required for the API request is available, you can send the request to call the API through **curl**, **Postman**, or coding. In the response to the API used to obtain a user token, **x-subject-token** is the desired user token. This token can then be used to authenticate the calling of other APIs.

## 3.2 Authentication

Requests for calling an API can be authenticated using either of the following methods:

- Token authentication: Requests are authenticated using tokens.
- AK/SK authentication: Requests are encrypted using AK/SK pairs. AK/SK authentication is recommended because it is more secure than token authentication.

#### **Token Authentication**

#### **NOTE**

The validity period of a token is 24 hours. When using a token for authentication, cache it to prevent frequently calling the IAM API used to obtain a user token.

A token specifies temporary permissions in a computer system. During API authentication using a token, the token is added to requests to get permissions for calling the API. You can obtain a token by calling the Obtaining User Token API.

A cloud service can be deployed as either a project-level service or global service.

- For a project-level service, you need to obtain a project-level token. When you call the API, set **auth.scope** in the request body to **project**.
- For a global service, you need to obtain a global token. When you call the API, set **auth.scope** in the request body to **domain**.

IMS is a project-level service. When you call the API, set **auth.scope** in the request body to **project**.

After a token is obtained, the **X-Auth-Token** header field must be added to requests to specify the token when calling other APIs. For example, if the token is **ABCDEFJ....**, **X-Auth-Token**: **ABCDEFJ....** can be added to a request as follows:

POST https://iam.ru-moscow-1.hc.sbercloud.ru/v3/auth/projects Content-Type: application/json X-Auth-Token: ABCDEFJ....

#### **AK/SK Authentication**

#### □ NOTE

AK/SK authentication supports API requests with a body not larger than 12 MB. For API requests with a larger body, token authentication is recommended.

In AK/SK authentication, AK/SK is used to sign requests and the signature is then added to the requests for authentication.

- AK: access key ID, which is a unique identifier used in conjunction with a secret access key to sign requests cryptographically.
- SK: secret access key, which is used in conjunction with an AK to sign requests cryptographically. It identifies a request sender and prevents the request from being modified.

In AK/SK authentication, you can use an AK/SK to sign requests based on the signature algorithm or using the signing SDK. For details about how to sign requests and use the signing SDK, see **API Request Signing Guide**.

#### □ NOTE

The signing SDK is only used for signing requests and is different from the SDKs provided by services.

## 3.3 Response

#### **Status Code**

After sending a request, you will receive a response, including a status code, response header, and response body.

A status code is a group of digits, ranging from 1xx to 5xx. It indicates the status of a request. For more information, see **Status Codes**.

For example, if status code **201** is returned for calling the API used to obtain a user token, the request is successful.

#### Response Header

Similar to a request, a response also has a header, for example, **Content-Type**.

**Figure 3-1** shows the response header fields for the API used to obtain a user token. The **x-subject-token** header field is the desired user token. This token can then be used to authenticate the calling of other APIs.

Figure 3-1 Header fields of the response to the request for obtaining a user token

```
connection → keep-alive

content-type → application/json

date → Tue, 12 Feb 2019 06:52:13 GMT

server → Web Server

strict-transport-security → max-age=31536000; includeSubdomains;

transfer-encoding → chunked

via → proxy A

x-content-type-options → nosniff

x-download-options → nospen

x-frame-options → SAMEORIGIN

x-iam-trace-id → 218d45ab-d674-4995-af3a-2d0255ba41b5

| x-subject-token → MITYXQYI/KoZlihvcNAQcColityTjCCGEoCAQExDTALBglghkgBZQMEAgEwgharBgkqhkiG9w0B8wGgghacBIIWmHsidG9rZW4iOnsiZXhwaXJlc19hdCl6tjJwMTktMDltMTNUMC
| ijiXls6vgKnpVNRbW2eZ5eb78SZOkqijACglkqOlw4JlGzrpd18LGXK5bdfq4lqHCYb8P4NaY0NYejcAgzJveFYttLWT1GSO0zxKzmlQHQig2HEqHdgjZO9fuEb15dMhday+33wEl
| x+RCE9187o+k9-
| ij-CMZ5E87bDLdG5Uj6eRASXI1jipPEGA270g1FruooL6jqglFkNPQuFSOU8+uSsttVwRtNfsC+qTp22Rkd5MCqFGQ8LcuUxC3a+9CMBnOintWW7oeRUVhVpxk8pxiX1wTEboX-
| Rzf6MUbpvGw-oPNFYxJECKnoH3HRozv0vN--n5d6Nbxg==

x-xss-protection → 1; mode=block;
```

#### (Optional) Response Body

The body of a response is often returned in structured format as specified in the **Content-Type** header field. The response body transfers content except the response header.

The following is part of the response body for the API used to obtain a user token.

If an error occurs during API calling, an error code and a message will be displayed. The following shows an error response body.

```
{
  "error_msg": "The format of message is error",
  "error_code": "AS.0001"
}
```

In the response body, **error\_code** is an error code, and **error\_msg** provides information about the error.

# 4 Getting Started

This section describes how to make API calls to create a private image from an ECS.

For details about how to call APIs, see Calling APIs.

#### **◯** NOTE

- Before using an ECS to create a private image, ensure that the ECS is stopped.
- The token obtained from IAM is valid for only 24 hours. If you want to use a token for authentication, you can cache it to avoid frequently calling the IAM API.

#### **Involved APIs**

If you use a token for authentication, you must obtain the token and add **X-Auth-Token** to the request header of the IMS API when making an API call.

- IAM API used to obtain the token
- IMS API used to create a private image

#### **Procedure**

- 1. Obtain the token by referring to **Authentication**.
- 2. Send **POST https://IMS endpoint/v2/cloudimages/action**.
- 3. Add X-Auth-Token to the request header.
- 4. Specify the following parameters in the request body:

```
{
  "name": "ims_test", //Image name (a mandatory string)
  "description": "Image creation from an ECS", //Image description (an optional string)
  "instance_id": "877a2cda-ba63-4e1e-b95f-e67e48b6129a", //ECS ID (a mandatory string)
  "tags": [
         "aaa.111",
         "bbb.333",
         "ccc.444"
  ] //Image tag list (optional, List<String>)
}
```

If the request is successful, a job ID is returned.

If the request fails, an error code and error information are returned. For details, see **Error Codes**.

- Query job details using the job ID by referring to Asynchronous Job Query.
   If the job status is SUCCESS, the private image is successfully created.
   For details about status codes for request exceptions, see Status Codes.
- 6. Obtain the image ID from the body of the job and query, delete, and export the private image using the image ID.

## 5 IMS APIS

## 5.1 Image

## 5.1.1 Querying Images

#### **Function**

This API is used to query images using search criteria and to display the images in a list.

#### URI

#### GET /v2/cloudimages{?

\_\_isregistered,\_\_imagetype,\_\_whole\_image,protected,visibility,owner,id,status,name ,container\_format,disk\_format,min\_ram,min\_disk,\_\_os\_bit,\_\_platform,marker,limit,s ort\_key,sort\_dir,\_\_os\_type,tag,member\_status,\_\_support\_kvm,\_\_support\_xen,\_\_support\_largememory,\_\_support\_diskintensive,\_\_support\_highperformance,\_\_support\_xen\_gpu\_type,\_\_support\_kvm\_gpu\_type,\_\_support\_xen\_hana,\_\_support\_kvm\_infiniban d,virtual\_env\_type,created\_at,updated\_at}

#### 

You can type a question mark (?) and an ampersand (&) at the end of the URI to define multiple search criteria. For details, see the example request.

Table 5-1 Parameter description

Paramete r	Mandato ry	Туре	Description
isregiste red	No	String	Specifies whether the image is available. The value can be <b>true</b> . The value is <b>true</b> for all extension APIs by default. Common users can query only the images for which the value of this parameter is <b>true</b> .
imagety pe	No	String	Specifies the image type. The following types are supported:
			<ul><li>Public image: The value is gold.</li><li>Private image: The value is private.</li></ul>
			Shared image: The value is shared.
			NOTE  Theimagetype of images you share with other tenants or those other tenants share with you and you have accepted is shared. You can use field owner to distinguish the two types of shared images. You can use member_status to filter out shared images you have accepted.
whole_i mage	No	Boolean	Specifies whether the image is a full-ECS image. The value can be <b>true</b> or <b>false</b> .
system_ _cmkid	No	String	Specifies the ID of the key used to encrypt the image. You can obtain the ID from the IMS console or by calling the Querying Image Details (Native OpenStack API) API.
protected	No	Boolean	Specifies whether the image is protected. The value can be <b>true</b> or <b>false</b> . Set it to <b>true</b> when you query public images. This parameter is optional when you query private images.
visibility	No	String	Specifies whether the image is available to other tenants. Available values include:  • public: public image  • private: private image  • shared: shared image
owner	No	String	Specifies the tenant to which the image belongs.
id	No	String	Specifies the image ID.

Paramete r	Mandato ry	Туре	Description
status	No	String	Specifies the image status. The value can be one of the following:
			queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.
			• <b>saving</b> : indicates that the image file is being uploaded to the backend storage.
			deleted: indicates that the image has been deleted.
			killed: indicates that an error occurs on the image uploading.
			active: indicates that the image is available for use.
name	No	String	Specifies the image name. Exact matching is used. For detailed description, see Image Attributes.
container_ format	No	String	Specifies the container type. The value is <b>bare</b> .
disk_form at	No	String	Specifies the image format. The value can be <b>zvhd2</b> , <b>vhd</b> , <b>zvhd</b> , <b>raw</b> , <b>iso</b> , or <b>qcow2</b> . The default value is <b>zvhd2</b> for a non-ISO image.
min_ram	No	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. Generally, the value is <b>0</b> .
min_disk	No	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.
os_bit	No	String	Specifies the OS architecture, 32 bit or 64 bit.
platform	No	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
marker	No	String	Specifies the start number from which images are queried. The value is the image ID.

Paramete r	Mandato ry	Туре	Description
limit	No	Integer	Specifies the number of images to be queried. The value is an integer and is <b>500</b> by default.
sort_key	No	String	Specifies the field for sorting the query results. The value can be an attribute of the image: name, container_format, disk_format, status, id, size, or created_at. The default value is created_at.
sort_dir	No	String	Specifies whether the query results are sorted in ascending or descending order. Its value can be <b>desc</b> (default) or <b>asc</b> . This parameter is used together with parameter <b>sort_key</b> . The default value is <b>desc</b> .
os_type	No	String	Specifies the image OS type. Available values include:  • Linux  • Windows  • Other
tag	No	String	Specifies a tag added to an image. Tags can be used as a filter to query images.  NOTE  The tagging function has been upgraded. If the tags added before the function upgrade are in the format of "Key.Value", query tags using "Key=Value". For example, an existing tag is a.b. After the tag function upgrade, query the tag using "tag=a=b".
member_s tatus	No	String	Specifies the member status. The value can be accepted, rejected, or pending. accepted: indicates that the shared image is accepted. rejected indicates that the image shared by others is rejected. pending indicates that the image shared by others needs to be confirmed. To use this parameter, set visibility to shared during the query.
support_ kvm	No	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_ xen	No	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.

Paramete r	Mandato ry	Туре	Description
support_ largemem ory	No	String	Specifies whether the image supports large-memory ECSs. If the image supports large-memory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.  For the supported OSs, see <b>Table 9-4</b> .
support_ diskintensi ve	No	String	Specifies whether the image supports disk-intensive ECSs. If the image supports disk-intensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_ highperfor mance	No	String	Specifies whether the image supports high-performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_ xen_gpu_t ype	No	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. See Table 9-2 for its value. If the image does not support GPU- accelerated ECSs on the Xen platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_ kvm_gpu_ type	No	String	Specifies whether the image supports GPU-accelerated ECSs on the KVM platform. See Table 9-3 for its value. If the image does not support GPU-accelerated ECSs on the KVM platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_ xen_hana	No	String	Specifies whether the image supports HANA ECSs on the Xen platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_ kvm_infini band	No	String	Specifies whether the image supports ECSs with the InfiniBand NIC on the KVM platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required. This attribute cannot co-exist withsupport_xen.

Paramete r	Mandato ry	Туре	Description
virtual_en v_type	No	String	Specifies the environment where the image is used. The value can be <b>FusionCompute</b> , <b>Ironic</b> , <b>DataImage</b> , or <b>IsoImage</b> .
			For an ECS image (system disk image), the value is <b>FusionCompute</b> .
			For a data disk image, the value is     DataImage.
			For a BMS image, the value is Ironic.
			For an ISO image, the value is IsoImage.
created_at	No	String	Specifies the time when the image was created. Images can be queried by time. The value is in the format of <i>Operator:UTC time</i> .
			The following operators are supported:
			• gt: greater than
			gte: greater than or equal to
			It: less than
			Ite: less than or equal to
			• eq: equal to
			neq: not equal to
			The time format is <i>yyyy-MM-</i> ddThh:mm:ssZ or yyyy-MM-dd hh:mm:ss.
			For example, to query images created before Oct 28, 2018 10:00:00, set the value of <b>created_at</b> as follows:
			created_at=lt:2018-10-28T10:00:00Z

Paramete r	Mandato ry	Туре	Description
updated_a t	No	String	Specifies the time when the image was modified. Images can be queried by time. The value is in the format of <i>Operator:UTC time</i> .
			The following operators are supported:
			• gt: greater than
			gte: greater than or equal to
			It: less than
			Ite: less than or equal to
			• eq: equal to
			neq: not equal to
			The time format is <i>yyyy-MM-</i> ddThh:mm:ssZ or yyyy-MM-dd hh:mm:ss.
			For example, to query images updated before Oct 28, 2018 10:00:00, set the value of <b>updated_at</b> as follows:
			updated_at=lt:2018-10-28T10:00:00Z

#### Request

• Request parameters

None

• Example request
GET https://{Endpoint}/v2/cloudimages?\_\_imagetype=gold&sort\_key=name&limit=1

## **Common Query Methods**

Public images
 GET /v2/cloudimages?\_\_imagetype=gold&visibility=public&protected=true

Private imagesGET /v2/cloudimages?owner={project\_id}

Available shared images

GET /v2/cloudimages? member\_status=accepted&visibility=shared&\_\_imagetype=shared

• Rejected images

GET /v2/cloudimages? member\_status=rejected&visibility=shared&\_\_imagetype=shared

Unaccepted images

GET /v2/cloudimages? member\_status=pending&visibility=shared&\_\_imagetype=shared

## Response

#### Response parameters

Parameter	Туре	Description
images	Array of objects	Specifies image details.
		For details, see <b>Table 5-2</b> .

Table 5-2 Data structure description of the images field

Parameter	Туре	Description
file	String	Specifies the URL for uploading and downloading the image file.
owner	String	Specifies the tenant to which the image belongs.
id	String	Specifies the image ID.
size	Long	This parameter is unavailable currently.
self	String	Specifies the image URL.
schema	String	Specifies the image schema.
status	String	Specifies the image status. The value can be one of the following:
		<ul> <li>queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.</li> </ul>
		<ul> <li>saving: indicates that the image file is being uploaded to the backend storage.</li> </ul>
		• <b>deleted</b> : indicates that the image has been deleted.
		<ul> <li>killed: indicates that an error occurs on the image uploading.</li> </ul>
		active: indicates that the image is available for use.

Parameter	Туре	Description
tags	Array of strings	Specifies tags of the image, through which you can manage private images in your own way. You can use the image tag API to add different tags to each image and filter images by tag.
visibility	String	Specifies whether the image is available to other tenants. Available values include:  • private: private image  • public: public image  • shared: shared image
name	String	Specifies the image name. For detailed description, see Image Attributes.
checksum	String	This parameter is unavailable currently.
protected	Boolean	Specifies whether the image is protected. A protected image cannot be deleted. The value can be <b>true</b> or <b>false</b> .
container_format	String	Specifies the container type.
min_ram	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. Generally, the value is <b>0</b> .
max_ram	String	Specifies the maximum memory (MB) of the image. You can set this parameter based on the ECS specifications. Generally, you do not need to set this parameter.
updated_at	String	Specifies the time when the image was updated. The value is in UTC format.
os_bit	String	Specifies the OS architecture, 32 bit or 64 bit.
os_version	String	Specifies the OS version.

Parameter	Туре	Description
description	String	Specifies the image description. For detailed description, see Image Attributes.
disk_format	String	Specifies the image format. The value can be zvhd2, vhd, zvhd, raw, iso, or qcow2. The default value is zvhd2 for a non-ISO image.
isregistered	String	Specifies whether the image has been registered. The value can be <b>true</b> or <b>false</b> .
platform	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
os_type	String	Specifies the OS type. The value can be <b>Linux</b> , <b>Windows</b> , or <b>Other</b> .
min_disk	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.
virtual_env_type	String	Specifies the environment where the image is used. The value can be FusionCompute, Ironic, Datalmage, or Isolmage.
		• For an ECS image, the value is <b>FusionCompute</b> .
		For a data disk image, the value is <b>DataImage</b> .
		For a BMS image, the value is <b>Ironic</b> .
		For an ISO image, the value is <b>IsoImage</b> .
image_source_type	String	Specifies the image backend storage type. Only UDS is supported currently.

Parameter	Туре	Description
imagetype	String	Specifies the image type. The following types are supported:
		<ul><li>Public image: The value is gold.</li><li>Private image: The value</li></ul>
		is <b>private</b> .
		Shared image: The value is <b>shared</b> .
created_at	String	Specifies the time when the image was created. The value is in UTC format.
virtual_size	Integer	This parameter is unavailable currently.
originalimagename	String	Specifies the parent image ID.
		If the image is a public image or created from an image file, this value is left empty.
backup_id	String	Specifies the backup ID. To create an image using a backup, set the value to the backup ID. Otherwise, this value is left empty.
image_size	String	Specifies the size (bytes) of the image file.
data_origin	String	Specifies the image source.  If the image is a public image, this parameter is left empty.
lazyloading	String	Specifies whether the image supports lazy loading. The value can be <b>true</b> , <b>false</b> , <b>True</b> , or <b>False</b> .
active_at	String	Specifies the time when the image status became <b>active</b> .
os_feature_list	String	Specifies additional attributes of the image. The value is a list (in JSON format) of advanced features supported by the image.

Parameter	Туре	Description
support_kvm	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xen	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_largememory	String	Specifies whether the image supports large-memory ECSs. If the image supports large-memory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_diskintensive	String	Specifies whether the image supports disk-intensive ECSs. If the image supports disk-intensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_highperforman ce	String	Specifies whether the image supports high-performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xen_gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. See Table 9-2 for its value. If the image does not support GPU-accelerated ECSs on the Xen platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.

Parameter	Туре	Description
support_kvm_gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the KVM platform. See Table 9-3 for its value.
		If the image does not support GPU-accelerated ECSs on the KVM platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_xen_hana	String	Specifies whether the image supports HANA ECSs on the Xen platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_kvm_infiniband	String	Specifies whether the image supports ECSs with the InfiniBand NIC on the KVM platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required. This attribute cannot co-exist with <b>support_xen</b> .
root_origin	String	Specifies that the image is created from an external image file. Value: <b>file</b>
sequence_num	String	Specifies the ECS system disk slot number corresponding to the image.  Example value: 0
support_fc_inject	String	Specifies whether the image supports password/private key injection using Cloud-Init.
		If the value is set to <b>true</b> , password/private key injection using Cloud-Init is not supported.
		NOTE  This parameter is valid only for ECS system disk images.

Parameter	Туре	Description
hw_firmware_type	String	Specifies the ECS boot mode. Available values include:
		• <b>bios</b> indicates the BIOS boot mode.
		uefi indicates the UEFI boot mode.
hw_vif_multiqueue_enabled	String	Specifies whether the image supports NIC multi-queue. The value can be <b>true</b> or <b>false</b> .
systemcmkid	String	Specifies the ID of the key used to encrypt the image.
support_amd	String	Specifies whether the image uses AMD's x86 architecture. The value can be <b>true</b> or <b>false</b> .

#### Example response

```
STATUS CODE 200
 "images": [
  "created_at": "2018-09-06T14:03:27Z",
    "__image_source_type": "uds",
"container_format": "bare",
     "file": "/v2/images/bc6bed6e-ba3a-4447-afcc-449174a3eb52/file",
    "updated_at": "2018-09-06T15:17:33Z",
    "protected": true,
     "checksum": "d41d8cd98f00b204e9800998ecf8427e",
     "id": "bc6bed6e-ba3a-4447-afcc-449174a3eb52",
    "__isregistered": "true",
    "min_ram": 2048,
    "_lazyloading": "true",
"owner": "1bed856811654c1cb661a6ca845ebc77",
    "_os_type": "Linux",
"_imagetype": "gold",
"visibility": "public",
"virtual_env_type": "FusionCompute",
    "tags": [],
"__platform": "CentOS",
    "size": 0,
    "__os_bit": "64",
"__os_version": "CentOS 7.3 64bit",
"name": "CentOS 7.3 64bit vivado",
"self": "/v2/images/bc6bed6e-ba3a-4447-afcc-449174a3eb52",
     "disk_format": "zvhd2",
     "virtual_size": null,
    "hw_firmware_type": "bios",
    "status": "active",
"__support_fc_inject":"true"
    "schema": "/v2/schemas/image", "min_disk": 100,
```

```
"created_at": "2018-09-06T14:03:05Z",
     "__image_source_type": "uds",
     "container_format": "bare",
     "file": "/v2/images/0328c25e-c840-4496-81ac-c4e01b214b1f/file", 
"updated_at": "2018-09-25T14:27:40Z",
     "protected": true,
     "checksum": "d41d8cd98f00b204e9800998ecf8427e",
     "id": "0328c25e-c840-4496-81ac-c4e01b214b1f",
     "__isregistered": "true",
     "min_ram": 2048,
     "_lazyloading": "true",
"owner": "1bed856811654c1cb661a6ca845ebc77",
     "__os_type": "Linux",
     "_imagetype": "gold",
     "visibility": "public",
"virtual_env_type": "FusionCompute",
     "tags": [],
     "__platform": "CentOS",
     "size": 0,
     "__os_bit": "64",
     "_os_version": "CentOS 7.3 64bit",
     "name": "CentOS 7.3 64bit with sdx",
     "self": "/v2/images/0328c25e-c840-4496-81ac-c4e01b214b1f",
     "disk_format": "zvhd2",
     "virtual_size": null,
     "hw_firmware_type": "bios",
    "status": "active",
     "__support_fc_inject":"true"
]
```

#### **Returned Values**

Normal

200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

## 5.1.2 Updating Image Information

#### **Function**

This API is used to modify image attributes and update image information.

#### **◯** NOTE

Only information of images in **active** status can be changed.

#### **URI**

PATCH /v2/cloudimages/{image\_id}

Table 5-3 describes the parameters in the URI.

Table 5-3 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Private image ID  For details about how to obtain the image ID, see Querying Images.

### Request

#### • Request parameters

Paramete r	Mandator y	Туре	Description
[Array]	Yes	Array of objects	For details, see <b>Table 5-4</b> .

Table 5-4 Data structure description of the [Array] field

Parameter	Mandatory	Туре	Description
ор	Yes	String	Specifies the operation. The value can be <b>add</b> , <b>replace</b> , or <b>remove</b> .

Parameter	Mandatory	Туре	Description
path	Yes	String	Specifies the name of the attribute to be modified. / needs to be added in front of it.
			You can modify the following attributes:
			• name: specifies the image name.
			•description: specifies the image description.
			•support_kvm: KVM is supported.
			•support_xen: Xen is supported.
			<ul> <li>support_diskintensive:         Intensive storage is supported.     </li> </ul>
			•support_highperformanc e: High-performance computing (HPC) is supported.
			<ul> <li>support_xen_gpu_type:         GPU-accelerated ECSs that         use Xen for virtualization         are supported.</li> </ul>
			<ul> <li>support_kvm_gpu_type:         GPU-accelerated ECSs that         use KVM for virtualization         are supported.</li> </ul>
			is_config_init: specifies     whether initialization     configuration is complete.
			• min_ram: specifies the minimum memory.
			• hw_vif_multiqueue_enable d: The NIC multi-queue feature is supported.
			<ul> <li>hw_firmware_type: specifies the boot mode. The value can be bios or uefi.</li> </ul>
			You can add or delete extension attributes.

Parameter	Mandatory	Туре	Description
value	Yes	String	Specifies the new value of the attribute. For detailed description, see Image Attributes.

```
Example request PATCH https://{Endpoint}/v2/cloudimages/33ad552d-1149-471c-8190-ff6776174a00 [
      "op": "replace",
"path": "/name",
"value": "ims_test"
]
```

### Response

#### Response parameters

Parameter	Туре	Description	
file	String	Specifies the URL for uploading and downloading the image file.	
owner	String	Specifies the tenant to which the image belongs.	
id	String	Specifies the image ID.	
size	Long	This parameter is unavailable currently.	
self	String	Specifies the image URL.	
schema	String	Specifies the image schema.	
status	String	Specifies the image status. The value can be one of the following:	
		queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.	
		saving: indicates that the image file is being uploaded to the backend storage.	
		deleted: indicates that the image has been deleted.	
		killed: indicates that an error occurs on the image uploading.	
		active: indicates that the image is available for use.	

Parameter	Туре	Description
tags	Array of strings	Specifies tags of the image, through which you can manage private images in your own way. You can use the image tag API to add different tags to each image and filter images by tag.
visibility	String	Specifies whether the image is available to other tenants. The value can be one of the following:
		private: private image
		public: public image
		• <b>shared</b> : shared image
name	String	Specifies the image name. For detailed description, see <b>Image Attributes</b> .
checksum	String	This parameter is unavailable currently.
protected	Boolean	Specifies whether the image is protected. A protected image cannot be deleted. The value can be <b>true</b> or <b>false</b> .
container_format	String	Specifies the container type.
min_ram	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. The default value is <b>0</b> .
max_ram	String	Specifies the maximum memory (MB) of the image. The parameter value depends on the ECS specifications and is not configured by default.
updated_at	String	Specifies the time when the image was updated. The value is in UTC format.
os_bit	String	Specifies the OS architecture, 32 bit or 64 bit.
os_version	String	Specifies the OS version.
description	String	Provides supplementary information about the image. For detailed description, see Image Attributes.
disk_format	String	Specifies the image format. The value can be <b>zvhd2</b> , <b>vhd</b> , <b>zvhd</b> , <b>raw</b> , <b>iso</b> , or <b>qcow2</b> . The default value is <b>zvhd2</b> for a non-ISO image.
isregistered	String	Specifies whether the image has been registered. The value can be <b>true</b> or <b>false</b> .

Parameter	Туре	Description
platform	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
os_type	String	Specifies the OS type. The value can be Linux, Windows, or Other.
systemcmkid	String	Specifies the ID of the key used to encrypt the image.
min_disk	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.
virtual_env_type	String	Specifies the environment where the image is used. The value can be <b>FusionCompute</b> , <b>Ironic</b> , <b>DataImage</b> , or <b>IsoImage</b> .
		• For an ECS image (system disk image), the value is <b>FusionCompute</b> .
		For a data disk image, the value is     DataImage.
		• For a BMS image, the value is <b>Ironic</b> .
		<ul> <li>For an ISO image, the value is IsoImage.</li> </ul>
image_source_typ	String	Specifies the backend storage of the image. Only UDS is supported currently.
imagetype	String	Specifies the image type. The following types are supported:
		Public image: The value is <b>gold</b> .
		<ul><li>Private image: The value is private.</li><li>Shared image: The value is shared.</li></ul>
created_at	String	Specifies the time when the image was created. The value is in UTC format.
virtual_size	Integer	This parameter is unavailable currently.
_originalimagena	String	Specifies the parent image ID.
me		If the image is a public image or created from an image file, this value is left empty.
backup_id	String	Specifies the backup ID. If the image is created from a backup, set the value to the backup ID. Otherwise, this parameter is not required.

Parameter	Туре	Description
image_size	String	Specifies the size (bytes) of the image file. The value must be greater than <b>0</b> .
data_origin	String	Specifies the image source.  If the image is a public image, this parameter is left empty.
root_origin	String	Specifies that the image is created from an external image file. Value: <b>file</b>
lazyloading	String	Specifies whether the image supports lazy loading. The value can be <b>true</b> , <b>false</b> , <b>True</b> , or <b>False</b> .
active_at	String	Specifies the time when the image status became <b>active</b> .
os_feature_list	String	Specifies additional attributes of the image. The value is a list (in JSON format) of advanced features supported by the image.
account_code	String	Specifies the charging identifier for the image.
hw_firmware_type	String	<ul> <li>Specifies the ECS boot mode. The following values are supported:</li> <li>bios indicates the BIOS boot mode. This value will be used by fault if this parameter does not exist in the response.</li> <li>uefi indicates the UEFI boot mode.</li> </ul>
hw_vif_multiqueue_ enabled	String	Specifies whether the image supports NIC multi-queue. The value can be <b>true</b> or <b>false</b> .
support_kvm	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xen	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_largeme mory	String	Specifies whether the image can be used to create large-memory ECSs. If the image supports large-memory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.  For the supported OSs, see <b>Table 9-4</b> .

Parameter	Туре	Description		
support_diskinten sive	String	Specifies whether the image can be used to create disk-intensive ECSs. If the image supports disk-intensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.		
support_highperf ormance	String	Specifies whether the image can be used to create high-performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.		
support_xen_gpu_ type	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. See <b>Table 9-2</b> for its value. If the image does not support GPU-accelerated ECSs on the Xen platform, this parameter is not required. This attribute cannot co-exist with <b>support_xen</b> and <b>support_kvm</b> .		
support_kvm_gpu _type	String	Specifies whether the image supports GPU-accelerated ECSs on the KVM platform. See Table 9-3 for its value. If the image does not support GPU- accelerated ECSs on the KVM platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.		
support_xen_hana	String	Specifies whether the image supports HANA ECSs on the Xen platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.		
support_kvm_infi niband	String	Specifies whether the image supports ECSs with the InfiniBand NIC on the KVM platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required. This attribute cannot co-exist withsupport_xen.		
sequence_num	String	Specifies the ECS system disk slot number corresponding to the image. This parameter is unavailable currently.		

Parameter	Туре	Description	
support_fc_inject	String	Specifies whether the image supports password/private key injection using Cloud-Init.	
		If the value is set to <b>true</b> , password/ private key injection using Cloud-Init is not supported.	
		NOTE  This parameter is valid only for ECS system disk images.	
support_amd	String	Specifies whether the image uses AMD's x86 architecture. The value can be <b>true</b> or <b>false</b> .	

### • Example response

```
STATUS CODE 200
   "file": "/v2/images/33ad552d-1149-471c-8190-ff6776174a00/file",
   "owner": "0b1e494e2660441a957313163095fe5c",
   "id": "33ad552d-1149-471c-8190-ff6776174a00",
   "size": 2,
   "self": "/v2/images/33ad552d-1149-471c-8190-ff6776174a00",
   "schema": "/v2/schemas/image",
   "status": "active",
   "tags": [],
   "visibility": "private",
"name": "ims_test",
"checksum": "99914b932bd37a50b983c5e7c90ae93b",
   "hw_vif_multiqueue_enabled": "true",
    "protected": false,
   "container_format": "bare",
   "min_ram": 0,
"updated_at": "2015-12-08T02:30:49Z",
   "updated_at": "2015-12-08102:30:492",
"_os_bit": "64",
"_os_version": "Ubuntu 14.04 server 64bit",
"_description": "ims test",
"disk_format": "vhd",
"_isregistered": "true",
"_platform": "Ubuntu",
"_os_type": "Linux",
"min_disk": 40
   "min_disk": 40,
   "virtual_env_type": "FusionCompute",
   "__image_source_type": "uds",
   "_imagetype": "private",
"created_at": "2015-12-04T09:45:33Z",
   "virtual_size": 0,
    "__originalimagename": "33ad552d-1149-471c-8190-ff6776174a00",
  "_backup_id": "",
"_productcode": "",
"_image_size": "449261568",
   "__support_fc_inject":"true",
   "_data_origin": null,
   "hw_firmware_type": "bios"
}
```

### **Returned Values**

Normal200

#### Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see Error Codes.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.1.3 Creating an Image

### **Function**

This API is used to create a private image. The following methods are supported:

- Create a system or data disk image from an ECS.
- Create a system disk image from an external image file uploaded to an OBS bucket.
- Create a system disk image from a data disk.

The API is an asynchronous one. If it is successfully called, the cloud service system receives the request. However, you need to use the asynchronous job query API to query the image creation status. For details, see **Asynchronous Job Query**.

# Constraints (Creating a System Disk Image Using a Data Disk)

- Before using a data disk to create a system disk image, ensure that an OS has been installed on the data disk and has been optimized. For details about the optimization, see "Optimizing a Windows Private Image" and "Optimizing a Linux Private Image" in the *Image Management Service User Guide*.
- The system cannot verify that an OS has been installed on the data disk. Therefore, ensure that the value of **os\_version** is valid when creating a system disk image from the data disk. For details, see **Values of Related Parameters**.

### **URI**

POST /v2/cloudimages/action

# Request

Parameters for creating a system or data disk image from an ECS

Parameter	Mandatory	Туре	Description
name	Yes	String	Specifies the name of the system disk image. For detailed description, see Image Attributes.
description	No	String	Specifies the image description. For details, see Image Attributes. The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. This parameter is left blank by default.
instance_id	Yes	String	Specifies the ID of the ECS used to create the image. To obtain the ECS ID, perform the following operations:  1. Log in to management console.  2. Under Computing, click Elastic Cloud Server.  3. In the ECS list, click the name of the ECS and view its ID.
data_images	No	Array of objects	Specifies the data disk information to be converted. This parameter is mandatory when the data disk of an ECS is used to create a private data disk image. For details, see Table 5-5.  If the ECS data disk is not used to create a data disk image, the parameter is empty by default.  NOTE  When you create a data disk image using a data disk, if other parameters (such as name, description, and tags) in this table have values, the system uses the value of data_images. You cannot specify instance_id.

Parameter	Mandatory	Туре	Description
tags	No	Array of strings	Specifies tags of the image. This parameter is left blank by default.
			Use either <b>tags</b> or <b>image_tags</b> .
image_tags	No	Array of objects	Specifies tags of the image. This parameter is left blank by default.
			Use either <b>tags</b> or <b>image_tags</b> .
max_ram	No	Integer	Specifies the maximum memory of the image in the unit of MB.
min_ram	No	Integer	Specifies the minimum memory of the image in the unit of MB. The default value is <b>0</b> , indicating that the memory is not restricted.

Table 5-5 Data structure description of the data\_images field

Parameter	Mandato ry	Туре	Description
name	Yes	String	Specifies the name of a data disk image.
volume_id	Yes	String	Specifies the data disk ID.
description	No	String	Specifies the data disk description.
tags	No	Array of strings	Specifies the data disk image tag.

Parameters for creating an image using an image file uploaded to the OBS bucket

Parameter	Mandatory	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.

Parameter	Mandatory	Туре	Description
description	No	String	Specifies the image description. For detailed description, see Image Attributes. The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. This parameter is left blank by default.
os_type	No	String	Specifies the OS type.
			The value can be <b>Linux</b> , <b>Windows</b> , or <b>Other</b> .
os_version	No	String	Specifies the OS version.  This parameter is valid if an external image file uploaded to the OBS bucket is used to create an image. For its value, see Values of Related Parameters.
			NOTE  If the uploaded file is in ISO format, this parameter is mandatory.
			This parameter is mandatory when the value of is_quick_import is true, that is, a system disk image is imported using the quick import method.

Parameter	Mandatory	Туре	Description
image_url	Yes	String	Specifies the URL of the external image file in the OBS bucket.
			This parameter is mandatory if an external image file in the OBS bucket is used to create an image. The format is OBS bucket name. Image file name.
			To obtain an OBS bucket name:
			<ol> <li>Log in to the management console and choose Storage &gt; Object Storage Service.</li> <li>All OBS buckets are displayed in the list.</li> </ol>
			2. Filter the OBS buckets by region and locate the target bucket in the current region.
			To obtain an OBS image file name:
			<ol> <li>Log in to the management console and choose Storage &gt; Object Storage Service.</li> <li>All OBS buckets are displayed in the list.</li> </ol>
			2. Filter the OBS buckets by region and locate the target bucket in the current region.
			3. Click the name of the target bucket to go to the bucket details page.
			4. In the navigation pane on the left, choose  Objects to display objects in the OBS bucket and then locate the external image file used to create an image.
			NOTE  The storage class of the OBS bucket must be <b>Standard</b> .

Parameter	Mandatory	Туре	Description
min_disk	Yes	Integer	Specifies the minimum size of the system disk in the unit of GB.  This parameter is mandatory if an external image file in the OBS bucket is used to create an image. The value ranges from 40 GB to 255 GB.
is_config	No	Boolean	Specifies whether automatic configuration is enabled. The value can be true or false. If automatic configuration is required, set the value to true. Otherwise, set the value to false The default value is false. For details about automatic configuration, see Creating a Linux System Disk Image from an External Image File > Registering an External Image File as a Private Image (Linux) in Image Management Service User Guide.
cmk_id	No	String	Specifies the master key used for encrypting an image. For its value, see the <i>Key Management Service User Guide</i> .
tags	No	Array of strings	Specifies tags of the image. The value is left blank by default. Use either tags or image_tags.
image_tags	No	Array of objects	Specifies tags of the image. This parameter is left blank by default. Use either tags or image_tags.
max_ram	No	Integer	Specifies the maximum memory of the image in the unit of MB.

Parameter	Mandatory	Туре	Description
min_ram	No	Integer	Specifies the minimum memory required by the image in the unit of MB. The default value is <b>0</b> , indicating that the memory is not restricted.
data_images	No	Array of objects	Specifies the data disk information to be imported.  An external image file can contain a maximum of three data disks. In this case, one system disk and three data disks will be created.  For details, see Table 5-6.  NOTE  If a data disk image file is used to create a data disk image, the OS type of the data disk image must be the same as that of the system disk image.  If other parameters (such as name, description, and tags) in Table 5-6 are set, the system uses the values in data_images.
is_quick_impo rt	No	Boolean	Specifies whether to use the quick import method to import a system disk image.  If yes, set the value to true.  If no, set the value to false.  For details about the restrictions on quick import of image files, see Importing an Image File Quickly.

**Table 5-6** Data structure description of the images field

Parameter	Manda tory	Туре	Description
name	No	String	Specifies the image name. For more details, see Image Attributes.

Parameter	Manda tory	Туре	Description
description	No	String	Specifies the image description. The value is left blank by default. The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. For more details, see Image
image_url	Yes	String	Specifies the URL of the external image file in the OBS bucket.  The format is OBS bucket name. Image file name.  To obtain an OBS bucket name:  1. Log in to the management console and choose Storage > Object Storage Service.  All OBS buckets are displayed in the list.  2. Filter the OBS buckets by region and locate the target bucket in the current region.  To obtain an OBS image file name:  1. Log in to the management console and choose Storage > Object Storage Service.  All OBS buckets are displayed in the list.  2. Filter the OBS buckets by region and locate the target bucket in the current region.  3. Click the name of the target bucket in the current region.  3. Click the name of the target bucket to go to the bucket details page.  4. In the navigation pane on the left, choose Objects to display objects in the OBS bucket and then locate the external image file used to create an image.  NOTE  The storage class of the OBS bucket must be Standard.

Parameter	Manda tory	Туре	Description
min_disk	Yes	Integer	Specifies the minimum size of the data disk.
			Unit: GB
			Value range: 1–2048
is_quick_import	No	Boolean	Specifies whether an image file is imported quickly to create a data disk image.
			If yes, set the value to <b>true</b> .
			If no, set the value to false.
			For details about the restrictions on quick import of image files, see Importing an Image File Quickly.
tags	No	Array of strings	Specifies tags of the image. The value is left blank by default.
			For detailed parameter descriptions, see Image Tag Data Formats.
			Use either <b>tags</b> or <b>image_tags</b> .
image_tags	No	Array of objects	Specifies tags of the image. The value is left blank by default.
			For detailed parameter descriptions, see Image Tag Data Formats.
			Use either <b>tags</b> or <b>image_tags</b> .

• Parameters for creating a system disk image using a data disk

Parameter	Mandator y	Туре	Description
name	Yes	String	Specifies the name of the system disk image. For more details, see Image Attributes.
volume_id	Yes	String	Specifies the data disk ID.

Parameter	Mandator y	Туре	Description
os_version	Yes	String	Specifies the OS version.  Set the parameter value based on Values of Related Parameters.  Otherwise, the created system disk image may be unavailable.  During the creation of a system disk image, if the OS can be detected from the data disk, the OS version in the data disk is used. In this case, the os_version value is invalid. If the OS can be detected from the data disk, the os_version value is used.
type	No	Sting	Specifies the image type.  The value can be ECS, BMS, FusionCompute, or Ironic.  • ECS and FusionCompute: indicates an ECS image.  • BMS and Ironic: indicates a BMS image.  The default value is ECS.
description	No	String	Specifies the image description. This parameter is left blank by default. For details, see Image Attributes. The image description must meet the following requirements:  Contains only letters and digits.  Cannot contain carriage returns and angle brackets (< >).  Cannot exceed 1024 characters.
min_ram	No	Integer	Specifies the minimum memory size (MB) required for running the image.  The parameter value depends on the ECS specifications. The default value is <b>0</b> .
max_ram	No	Integer	Specifies the maximum memory size (MB) required for running the image.  The parameter value depends on the ECS specifications. The default value is <b>0</b> .

Parameter	Mandator y	Туре	Description
tags	No	Array of strings	Specifies tags of the image. This parameter is left blank by default.  Use either tags or image_tags.
image_tags	No	Array of objects	Specifies tags of the image. This parameter is left blank by default.  Use either tags or image_tags.

#### Example requests

Request for creating a system disk image with parameter tags using an ECS

```
POST https://{Endpoint}/v2/cloudimages/action

{
    "name": "ims_test",
    "description": "Create a system disk image from an ECS",
    "instance_id": "877a2cda-ba63-4e1e-b95f-e67e48b6129a",
    "tags": [
        "aaa.111",
        "bbb.333",
        "ccc.444"
        ]
}
```

 Request for creating a data disk image with parameter tags using the data disk of an ECS

```
POST https://{Endpoint}/v2/cloudimages/action

{

"data_images": [{"name": "ims_data_image_test",

"description": "Create a data disk image from the data disk of an ECS",

"volume_id": "c5dfbd0c-bf0a-4798-a453-61dc6b54aa30",

"tags": [

"aaa.111",

"bbb.333",

"ccc.444"

]

}]
```

 Request for creating an image with parameter tags using an external image file uploaded to the OBS bucket

Request for creating a system disk image with parameter image\_tags using an ECS

```
POST https://{Endpoint}/v2/cloudimages/action
{
    "name": "ims_test",
    "description": "Create a system disk image from an ECS",
```

 Request for creating a data disk image with parameter image\_tags using the data disk of an ECS

```
POST /v2/cloudimages/action

{

    "data_images": [{"name": "ims_data_image_test",
    "description": "Create a data disk image from the data disk of an ECS",
    "volume_id": "c5dfbd0c-bf0a-4798-a453-61dc6b54aa30",
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}]
    }]
}
```

Request for creating an image with parameter image\_tags using an external image file uploaded to the OBS bucket

```
POST https://{Endpoint}/v2/cloudimages/action

{
    "name": "ims_test_file",
    "description": "Create an image from a file in the OBS bucket",
    "image_url": "ims-image:centos70.qcow2",
    "os_version": "CentOS 7.0 64bit",
    "min_disk": 40,
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}]
}
```

 Request for creating a system disk image with parameter tags using a data disk

Request for creating a system disk image with parameter image\_tags using a data disk

```
POST https://{Endpoint}/v2/cloudimages/action

{
    "name": "ims_test",
    "description": "Create a system disk image from a data disk",
    "volume_id": "877a2cda-ba63-4e1e-b95f-e67e48b6129a",
    "type": "ECS",
    "os_version": "CentOS 7.0 64bit",
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}]
}
```

# Response

Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID. For details, see <b>Asynchronous Job Query</b> .

Example response

```
STATUS CODE 200
{
    "job_id": "8a12fc664fb4daa3014fb4e581380005"
}
```

### **Returned Values**

- Normal200
- Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see Error Codes.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.1.4 Importing an Image File Quickly

### **Function**

This API is used to quickly create a private image from an oversized external image file that has uploaded to the OBS bucket. Currently, only ZVHD2 and RAW image files are supported, and the size of an image file cannot exceed 1 TB.

The fast image creation function is only available for image files in RAW or ZVHD2 format. For other formats of image files that are smaller than 128 GB, you are advised to import these files with the common method.

The API is an asynchronous one. If it is successfully called, the cloud service system receives the request. However, you need to use the asynchronous job query API to query the image creation status. For details, see **Asynchronous Job Query**.

### **Constraints**

Before importing image files, ensure that the file format is RAW or ZVHD2 and the following have been done:

- RAW image files have been optimized, and bitmap files have been generated.
- ZVHD2 image files have been optimized as required.

## □□ NOTE

For how to convert image file formats and generate a bitmap file, see section "Quickly Importing an Image File" in the *Image Management Service User Guide*.

# URI

POST /v2/cloudimages/quickimport/action

# Request

• Parameters in the request body when an image file is used to create a system disk image

Parameter	Mandator y	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.
description	No	String	Provides supplementary information about the image.
			For detailed description, see Image Attributes.
			The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. This parameter is left blank by default.
os_version	Yes	String	Specifies the OS version.
			This parameter is valid if an external image file uploaded to the OBS bucket is used to create an image. For its value, see Values of Related Parameters.

Parameter	Mandator y	Туре	Description
image_url	Yes	String	Specifies the URL of the external image file in the OBS bucket.
			This parameter is mandatory if an external image file in the OBS bucket is used to create an image. The format is OBS bucket name.Image file name.  NOTE  The storage class of the OBS
			bucket must be <b>Standard</b> .
min_disk	Yes	Integer	Specifies the minimum size (GB) of the system disk.
			<ul> <li>This parameter is mandatory if an external image file in the OBS bucket is used to create an image.</li> </ul>
			The value ranges from 1 to 1024 and must be greater than the size of the selected image file.
tags	No	Array of strings	Lists the image tags. This parameter is left blank by default.
			Set either <b>tags</b> or <b>image_tags</b> .
image_tags	No	Array of objects	Lists the image tags. The value is left blank by default.
		j	Set either <b>tags</b> or <b>image_tags</b> .
type	No	String	Specifies the image type. The parameter value is ECS/BMS for system disk images. The default value is <b>ECS</b> .

Parameter	Mandator y	Туре	Description
architecture	No	String	Specifies the image architecture type. Available values include:  • x86  • arm  The default value is x86.  NOTE  If the image architecture is ARM, the boot mode is automatically changed to UEFI.

 Parameters description when an image file uploaded to the OBS bucket is used to create an image

Parameter	Mandator y	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.
description	No	String	Provides supplementary information about the image. For detailed description, see Image Attributes. The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. This parameter is left blank by default.
os_type	No	String	Specifies the OS version.  When a data disk image created, the value can be Linux or Windows. The default is Linux.

Parameter	Mandator y	Туре	Description
image_url	Yes	String	Specifies the URL of the external image file in the OBS bucket.
			This parameter is mandatory if an external image file in the OBS bucket is used to create an image. The format is OBS bucket name.Image file name.
			NOTE  The storage class of the OBS bucket must be <b>Standard</b> .
min_disk	Yes	Integer	Specifies the minimum size of the system disk in the unit of GB.
			This parameter is mandatory if an external image file in the OBS bucket is used to create an image. The value ranges from 1 to 1024.
tags	No	Array of strings	Lists the image tags. This parameter is left blank by default.
			Set either <b>tags</b> or <b>image_tags</b> .
image_tags	No	Array of objects	Lists the image tags. The value is left blank by default.
			Set either <b>tags</b> or <b>image_tags</b> .
type	Yes	String	Specifies the image type. The parameter value is DataImage for data disk images.

## • Example requests

 Creating a system disk image using an external image file POST https://{Endpoint}/v2/cloudimages/quickimport/action

### If parameter tags is used:

```
{
    "name": "ims_test_file",
    "description": "Create an image using a file in the OBS bucket.",
    "image_url": "ims-image:centos70.zvhd2",
    "os_version": "CentOS 7.0 64bit",
    "min_disk": 40,
    "type": "ECS",
    "tags":
    [
```

```
"aaa.111",
"bbb.333",
"ccc.444"
]
```

### If parameter **image\_tags** is used:

```
{
    "name": "ims_test_file",
    "description": "Create an image using a file in the OBS bucket.",
    "image_url": "ims-image:centos70.zvhd2",
    "os_version": "CentOS 7.0 64bit",
    "min_disk": 40,
    "type": "ECS",
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}]
}
```

 Creating a data disk image using an external image file POST https://{Endpoint}/v2/cloudimages/quickimport/action

#### If parameter tags is used:

## If parameter image\_tags is used:

```
{
  "name": "ims_test_file",
  "description": "Create an image using a file in the OBS bucket.",
  "image_url": "ims-image:centos70.qcow2",
  "os_type": "Linux",
  "min_disk": 40,
  "type": "DataImage",
  "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}]
}
```

# Response

• Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID.
		For details, see <b>Asynchronous Job Query</b> .

Example response
 STATUS CODE 200
 "job\_id": "8a12fc664fb4daa3014fb4e581380005"

### **Returned Values**

Normal

### 200

#### Abnormal

Return Value	Description
400 Bad Request	Request error. For details about the returned error code, see Error Codes.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.1.5 Creating a Data Disk Image Using an External Image File

# **Function**

This API is used to create a data disk image from a data disk image file uploaded to the OBS bucket. The API is an asynchronous one. If it is successfully called, the cloud service system receives the request. However, you need to use the asynchronous job query API to query the image creation status. For details, see Asynchronous Job Query.

## **URI**

POST /v1/cloudimages/dataimages/action

# Request

#### Request parameters

Parameter	Mandatory	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.
description	No	String	Provides supplementary information about the image. For detailed description, see Image Attributes. The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. This parameter is left blank by default.

2023-02-13

Parameter	Mandatory	Туре	Description
os_type	No	String	Specifies the OS type. It can only be Windows or Linux.
			The default is Linux.
image_url	Yes	String	Specifies the URL of the external image file in the OBS bucket.
			The format is <i>OBS bucket</i> name.Image file name.
			NOTE  The storage class of the OBS bucket must be <b>Standard</b> .
min_disk	Yes	Integer	Specifies the minimum size of the data disk.
			Value range: 40 GB to 2048 GB
cmk_id	No	String	Specifies the master key used for encrypting an image. For its value, see the <i>Key Management Service User Guide</i> .
tags	No	Array of strings	Specifies image tags. This parameter is left blank by default.
			For detailed parameter description, see Image Tag Data Formats.
			Use either <b>tags</b> or <b>image_tags</b> .
image_tags	No	Array of ImageTa g objects	Lists the image tags. This parameter is left blank by default.
		g objects	Use either <b>tags</b> or <b>image_tags</b> .

Table 5-7 Data structure description of the image\_tags field

Parameter	Mandatory	Туре	Description
key	No	string	Specifies the tag key.
value	No	string	Specifies the tag value.

# • Example requests

Request for creating an image (tags)

POST https://{Endpoint}/v1/cloudimages/dataimages/action

{
 "name": "fedora-data1",
 "image\_url": "image-test:fedora\_data1.qcow2",
 "description":"Data disk 1 of Fedora",
 "min\_disk": 40,
 "tags": [

```
"aaa.111",
"bbb.222"
],
"os_type": "Linux"
}
```

Request for creating an image (image\_tags)

```
POST https://{Endpoint}/v1/cloudimages/dataimages/action
{
    "name": "fedora-data2",
    "image_url": "image-test:fedora_data1.qcow2",
    "description":"Data disk 2 of Fedora",
    "min_disk": 40,
    "image_tags": [{"key":"aaa","value":"111"},{"key":"bbb","value":"222"}],
    "os_type": "Linux"
}
```

# Response

Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID. For details, see <b>Asynchronous Job Query</b> .

Example response

```
STATUS CODE 200
{
  "job_id": "4010a32b5f909853015f90aaa24b0015"
}
```

# **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see Error Codes.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.1.6 Creating a Full-ECS Image

## **Function**

This API is used to create a full-ECS image from an ECS or a CBR backup. The API is an asynchronous one. If it is successfully called, the cloud system receives the request to create a full-ECS image. However, you need to use the asynchronous job query API to query the image creation status. For details, see **Asynchronous Job Query**.

# Constraints (Creating a Full-ECS Image Using an ECS)

- When creating a full-ECS image from an ECS, ensure that the ECS has been properly configured, or the image creation may fail.
- A Windows ECS used to create a full-ECS image cannot have a spanned volume, or data may be lost when ECSs are created from that image.
- A Linux ECS used to create a full-ECS image cannot have a disk group or logical disk that contains multiple physical disks, or data may be lost when ECSs are created from that image.
- A full-ECS image cannot be replicated within a region or be exported.
- When creating a full-ECS image from a Windows ECS, you need to change the SAN policy of the ECS to OnlineAll. Otherwise, EVS disks attached to the ECSs created from the image may be offline.

Windows has three types of SAN policies: **OnlineAll**, **OfflineShared**, and **OfflineInternal**.

Table 5-8 SAN policies in Windows

Туре	Description
OnlineAll	All newly detected disks are automatically brought online.
OfflineSh ared	All disks on sharable buses, such as iSCSI and FC, are left offline by default, while disks on non-sharable buses are kept online.
OfflineIn ternal	All newly detected disks are left offline.

a. Execute **cmd.exe** and run the following command to query the current SAN policy of the ECS:

#### diskpart

b. Run the following command to view the SAN policy of the ECS:

#### san

- If the SAN policy is OnlineAll, run the exit command to exit DiskPart.
- If the SAN policy is not OnlineAll, go to c.
- c. Run the following command to change the SAN policy of the ECS to **OnlineAll**:

### san policy=onlineall

# Constraints (Creating a Full-ECS Image Using a CBR Backup)

- When creating a full-ECS image from a CBR backup, ensure that the source ECS of the CBR backup has been properly configured, or the image creation may fail.
- A CBR backup can be used to create only one full-ECS image.
- If an ECS is in **Stopped** state, do not start it when you are using it to create a full-ECS image.
- A full-ECS image created from a CBR backup can be shared with other tenants. However, if it is a shared CBR backup, the full-ECS image created from it cannot be shared.
- A full-ECS image cannot be replicated within a region or be exported.

## URI

POST /v1/cloudimages/wholeimages/action

# Request

Parameters for creating a full-ECS image using an ECS

Parameter	Mandatory	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.
description	No	String	Provides supplementary information about the image. For detailed description, see Image Attributes.
tags	No	Array of strings	Lists the image tags. The value is left blank by default. Use either tags or image_tags.
image_tags	No	Array of objects	Lists the image tags. The value is left blank by default. Use either tags or image_tags.

Parameter	Mandatory	Туре	Description
instance_id	Yes	String	Specifies the ECS ID. This parameter is required when an ECS is used to create a full-ECS image.
			To obtain the ECS ID, perform the following operations:
			1. Log in to management console.
			2. Under <b>Computing</b> , click <b>Elastic Cloud Server</b> .
			3. In the ECS list, click the name of the ECS and view its ID.
max_ram	No	Integer	Specifies the maximum memory of the image in the unit of MB. This parameter is not configured by default.
min_ram	No	Integer	Specifies the minimum memory of the image in the unit of MB. The default value is <b>0</b> .
vault_id	Yes	String	Specifies the ID of the vault to which an ECS is to be added or has been added.
			You can obtain the vault ID from the CBR console or section "Querying the Vault List" in <i>Cloud Backup and Recovery API Reference</i> .

 Parameters in the request body when a CBR backup is used to create a full-ECS image

Parameter	Mandatory	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.
description	No	String	Provides supplementary information about the image. For detailed description, see Image Attributes.
tags	No	Array of strings	Lists the image tags. The value is left blank by default. Use either tags or image_tags.

Parameter	Mandatory	Туре	Description
image_tags	No	Array of objects	Lists the image tags. The value is left blank by default.  Use either tags or image_tags.
backup_id	Yes	String	Specifies the CBR backup ID. To obtain the CBR backup ID, perform the following operations:  1. Log in to the management console.  2. Under Storage, click Cloud Backup and Recovery.  3. On the displayed Cloud Server Backup page, click the Backups tab and obtain the backup list.
max_ram	No	Integer	Specifies the maximum memory of the image in the unit of MB. This parameter is not configured by default.
min_ram	No	Integer	Specifies the minimum memory of the image in the unit of MB. The default value is <b>0</b> , indicating that the memory is not restricted.
whole_image _type	Yes	String	Specifies the method of creating the full-ECS image. The value must be <b>CBR</b> .

## • Example requests

Creating a full-ECS image from an ECS
 POST https://{Endpoint}/v1/cloudimages/wholeimages/action

## If parameter **tags** is used:

# If parameter image\_tags is used:

```
{
    "name": "instance_whole_image",
    "description": "creating an image from an ECS",
```

```
"instance_id": "877a2cda-ba63-4e1e-b95f-e67e48b6129a",
    "vault_id": "de9fcf45-11b2-432c-8562-5c5428574600",
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}]
}
```

 Creating a full-ECS image using a CBR backup POST https://{Endpoint}/v1/cloudimages/wholeimages/action

### If parameter tags is used:

```
{
  "name": "backup_whole_image",
  "description": "Creating a full-ECS image using a CBR backup",
  "backup_id": "9b27efab-4a17-4c06-bfa2-3e0cf021d3c3",
  "whole_image_type": "CBR",
  "tags": [
         "aaa.111",
         "bbb.333",
         "ccc.444"
  ]
}
```

### If parameter image\_tags is used:

```
{
    "name": "backup_whole_image",
    "description": "Creating a full-ECS image using a CBR backup",
    "backup_id": "9b27efab-4a17-4c06-bfa2-3e0cf021d3c3",
    "whole_image_type": "CBR",
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}]
}
```

# Response

• Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID. For details, see <b>Asynchronous Job Query</b> .

```
• Example response
```

```
STATUS CODE 200
{
    "job_id": "4010a32b5f909853015f90aaa24b0015"
}
```

## **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.

Returned Value	Description
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.1.7 Registering an Image

### **Function**

This API is used to register an image file as an uninitialized private image on the cloud platform.

The following describes how to use this API:

- 1. Upload the image file to an OBS bucket. For details, see "Object Storage Service User Guide".
- 2. Use the image metadata creation API to create image metadata. After the API is invoked successfully, save the image ID. For how to create image metadata, see Creating Image Metadata (Native OpenStack API).
- 3. Use the API for registering images and the image ID obtained in 2 to register the image file as a private image.
- 4. After the API is successfully invoked as an asynchronous one, the cloud service system receives a request. Query the image status using the image ID and check whether the image file is successfully registered. When the image status changes to **active**, the image file is successfully registered as a private image. For details about how to query the status of an asynchronous task, see

#### ■ NOTE

Before registering an image file, ensure that you have the Tenant Administrator permission for OBS.

### **URI**

PUT /v1/cloudimages/{image id}/upload

**Asynchronous Job Query.** 

Table 5-9 lists the parameters in the URI.

**Table 5-9** Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	<ul> <li>specifies the image ID.</li> <li>image_id is the ID of the image you created by invoking the API for creating image metadata.</li> </ul>
			Registration may fail if you use other image IDs.  • After this API is invoked, you can check the image status with the image ID. When the image status changes to active, the image file is successfully registered. For details, see Querying Image Details (Native OpenStack API).

# Request

• Request parameters

Parameter	Mandatory	Туре	Description
image_url	Yes	String	Specifies the URL of the image file in the format of <i>Bucket name</i> . File name.
			Image files in the bucket can be in ZVHD, QCOW2, VHD, RAW, VHDX, QED, VDI, QCOW, ZVHD2, ISO, or VMDK format.
			NOTE  The storage class of the OBS bucket must be <b>Standard</b> .

• Example request

```
PUT https://{Endpoint}/v1/cloudimages/4ca46bf1-5c61-48ff-b4f3-0ad4e5e3ba86/upload {
    "image_url": "bucketname:Centos6.5-disk1.vmdk"
```

# Response

• Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID. For details, see <b>Asynchronous Job Query</b> .

• Example response

```
HTTP/1.1 200 {
    "job_id":" b912fb4a4c464b568ecfca1071b21b10"
 }
```

## **Returned Values**

- Normal200
- Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see Error Codes.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.

# 5.1.8 Exporting an Image

## **Function**

This is an extension API and used to export a private image to an OBS bucket.

#### □ NOTE

Before exporting an image, ensure that you have the Tenant Administrator permission for OBS.

### **Constraints**

- The following private images cannot be exported:
  - Full-ECS images
  - ISO images
  - Private images created from a Windows, SUSE, Red Hat, Ubuntu, or Oracle Linux public image
- The image size must be less than 1 TB. Images larger than 128 GB support only fast export.

## **URI**

POST /v1/cloudimages/{image\_id}/file

Table 5-10 lists the parameters in the URI.

Table 5-10 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.  For details about how to obtain the image ID, see Querying Images.

# Request

• Request parameters

Parameter	Mandatory	Туре	Description
bucket_url	Yes	String	Specifies the URL of the image file in the format of Bucket name: File name.  NOTE  The storage class of the OBS bucket must be Standard.
file_format	Yes	String	Specifies the file format. The value can be <b>qcow2</b> , <b>vhd</b> , <b>zvhd</b> , or <b>vmdk</b> .
is_quick_expo rt	No	Boolean	Whether to enable fast export. The value can be <b>true</b> or <b>false</b> . <b>NOTE</b> If fast export is enabled, <b>file_format</b> cannot be specified.

Example request

```
POST https://{Endpoint}/v1/cloudimages/d164b5df-1bc3-4c3f-893e-3e471fd16e64/file {
    "bucket_url": "ims-image:centos7_5.qcow2",
    "file_format": "qcow2",
    "is_quick_export": false
}
```

# Response

• Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID. For details, see <b>Asynchronous Job Query</b> .

• Example response

```
STATUS CODE 200 {
    "job_id": "edc89b490d7d4392898e19b2deb34797"
}
```

# **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see Error Codes.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# **5.1.9 Querying Supported Image OSs**

# **Function**

This interface is used to query the list of compatible ECS OSs in the current region.

# URI

GET /v1/cloudimages/os\_version

Table 5-11 Parameter description

Parameter	Mandator y	Туре	Description
tag No	String	Specifies the OS tag.  You can query OSs with specified features based on the tag value. Possible values are	
			as follows:  • bms: indicates the BMS OS versions supported by the image.
		uefi: indicates the OS     versions that support the     UEFI boot mode.	
			If this parameter is not specified, all the supported OSs in the current region are to be queried.

# Request

- Request parameters
  - None
- Example request
  - Querying supported OSs
     GET https://{Endpoint}/v1/cloudimages/os\_version
  - Querying supported OSs by filters
     GET https://{Endpoint}/v1/cloudimages/os\_version?tag=kvm&tag=uefi

# Response

• Response parameters

Parameter	Туре	Description
[Array]	Array of objects	For details, see <b>Table 5-12</b> .

Table 5-12 Data structure description of the [Array] field

Parameter	Туре	Description
platform	String	Specifies the OS platform.
version_list	Array of objects	Specifies the returned OS details. For details, see <b>Table 5-13</b> .

Table 5-13 Data structure de	escription of	the [Array].ve	ersion list field
------------------------------	---------------	----------------	-------------------

Parameter	Туре	Description
platform	String	Specifies the OS platform.
os_version_key	String	Specifies the key value of the OS. The default key value is the value of os_version.
os_version	String	Specifies the complete OS information.
os_bit	Integer	Specifies the OS bit.
os_type	String	Specifies the OS type.

## • Example response

```
STATUS CODE 200
       "platform": "SUSE",
       "version_list": [
           {
               "platform": "SUSE",
               "os_version_key": "SUSE Linux Enterprise Server 15 64bit",
"os_version": "SUSE Linux Enterprise Server 15 64bit",
               "os_bit": 64,
               "os_type": "Linux"
           },
{
               "platform": "SUSE",
               "os_version_key": "SUSE Linux Enterprise Server 12 SP3 64bit", "os_version": "SUSE Linux Enterprise Server 12 SP3 64bit",
               "os_bit": 64,
               "os_type": "Linux"
          }
       ]
   },
{
       "platform": "Other",
       "version_list": [
               "platform": "Other",
               "os_version_key": "Other(32 bit)",
"os_version": "Other(32 bit)",
               "os_bit": 32,
"os_type": "Linux"
          }
      ]
```

## **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.2 Image Sharing

# **5.2.1 Deleting Image Members in Batches**

#### **Function**

This API is an extension one and used to stop sharing images by deleting tenants with whom the image is shared in batches.

This API is an asynchronous one. If **job\_id** is returned, the task is successfully delivered. You need to query the status of the asynchronous task. If the status is **success**, the task is successfully executed. If the status is **failed**, the task fails. For details about how to query the status of an asynchronous task, see **Asynchronous Job Query**.

#### URI

DELETE /v1/cloudimages/members

# Request

## • Request parameters

Parameter	Mandatory	Туре	Description
images	Yes	Array of strings	Specifies the image IDs.
projects	Yes	Array of strings	Specifies the project IDs.

#### • Example request

```
DELETE https://{Endpoint}/v1/cloudimages/members
{
"images": [
"d164b5df-1bc3-4c3f-893e-3e471fd16e64",
```

# Response

Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous task ID. For details, see Asynchronous Job Query.

```
    Example response
    STATUS CODE 200
    "job_id": "edc89b490d7d4392898e19b2deb34797"
    }
```

#### **Returned Values**

- Normal200
- Abnormal

Returned Value	Description
400 Bad Request	Request error. For details, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# **5.2.2 Adding Image Members in Batches**

#### **Function**

This API is an extension one and used to share more than one image with multiple tenants.

This API is an asynchronous one. If **job\_id** is returned, the task is successfully delivered. You need to query the status of the asynchronous task. If the status is **success**, the task is successfully executed. If the status is **failed**, the task fails. For

details about how to query the status of an asynchronous task, see **Asynchronous Job Query**.

## **URI**

POST /v1/cloudimages/members

# Request

#### Request parameters

Parameter	Mandatory	Туре	Description
images	Yes	Array of strings	Specifies the image IDs.
projects	Yes	Array of strings	Specifies the project IDs.

• Example request

```
POST https://{Endpoint}/v1/cloudimages/members

{
    "images": [
        "d164b5df-1bc3-4c3f-893e-3e471fd16e64",
        "0b680482-acaa-4045-b14c-9a8c7dfe9c70"
    ],
    "projects": [
        "9c61004714024f9586705d090530f9fa",
        "edc89b490d7d4392898e19b2deb34797"
    ]
}
```

# Response

Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous task ID. For details, see Asynchronous Job
		Query.

• Example response STATUS CODE 200

```
{
    "job_id": "edc89b490d7d4392898e19b2deb34797"
    }
```

# **Returned Values**

Normal

200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.2.3 Updating the Status of Image Members in Batches

## **Function**

This API is an extension one and used to update the image sharing status after the tenant accepts or rejects the shared images.

This API is an asynchronous one. If **job\_id** is returned, the task is successfully delivered. You need to query the status of the asynchronous task. If the status is **success**, the task is successfully executed. If the status is **failed**, the task fails. For details about how to query the status of an asynchronous task, see **Asynchronous Job Query**.

#### URI

PUT /v1/cloudimages/members

# Request

#### Request parameters

Parameter	Mandatory	Туре	Description
images	Yes	Array of strings	Specifies the image IDs.
project_id	Yes	String	Specifies the project ID.

Parameter	Mandatory	Туре	Description
status	Yes	String	Specifies whether a shared image will be accepted or declined.
			The value can be one of the following:
			accepted: indicates that a shared image is accepted. After an image is accepted, the image is displayed in the image list. You can use the image to create ECSs.
			• rejected: indicates that a shared image is declined. After an image is declined, the image is not displayed in the image list.  However, you can still use the image to create ECSs.
vault_id	Yes	String	Specifies the vault ID. You can obtain the vault ID from the CBR console or section "Querying the Vault List" in <i>Cloud</i> Backup and Recovery API Reference.

#### Example request

```
If the shared images do not include full-ECS images: PUT https://{Endpoint}/v1/cloudimages/members
         "d164b5df-1bc3-4c3f-893e-3e471fd16e64",
"0b680482-acaa-4045-b14c-9a8c7dfe9c70"
      "project_id": "edc89b490d7d4392898e19b2deb34797",
"status": "accepted"
```

If the shared images include full-ECS images:

```
PUT https://{Endpoint}/v1/cloudimages/members
 "images": [
    "d164b5df-1bc3-4c3f-893e-3e471fd16e64",
    "0b680482-acaa-4045-b14c-9a8c7dfe9c70"
  "vault_id": "d14r5tef-1bc3-4c4f-823e-3e471rg65e65"
```

# Response

Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID. For details, see <b>Asynchronous Job Query</b> .

Example response

STATUS CODE 200

{
 "job\_id": "edc89b490d7d4392898e19b2deb34797"

## **Returned Values**

- Normal200
- Abnormal

Returned Value	Description
400 Bad Request	Request error. For details, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.3 Image Replication

# 5.3.1 Replicating an Image Within a Region

# **Function**

This API is an extension one and is used to copy an existing image to another image. When replicating an image, you can change the image attributes to meet the requirements of different scenarios.

This API is an asynchronous one. If **job\_id** is returned, the task is successfully delivered. You need to query the status of the asynchronous task. If the status is **success**, the task is successfully executed. If the status is **failed**, the task fails. For details about how to query the status of an asynchronous task, see **Asynchronous Job Query**.

## **Constraints**

- Full-ECS images cannot be replicated within the same region.
- Private images created using ISO files do not support in-region replication.

## **URI**

POST /v1/cloudimages/{image\_id}/copy

Table 5-14 lists the parameters in the URI.

Table 5-14 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.  For details about how to obtain the image ID, see Querying Images.

# Request

# • Request parameters

Parameter	Mandatory	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.
description	No	String	Provides supplementary information about the image. For detailed description, see Image Attributes. The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. This parameter is left blank by default.
cmk_id	No	String	Specifies the encryption key. This parameter is left blank by default.

#### • Example request

POST https://{Endpoint}/v1/cloudimages/465076de-dc36-4aec-80f5-ef9d8009428f/copy {

"name": "ims\_encrypted\_copy3",

```
"description": "test copy",
    "cmk_id": "bd66288c-9081-460a-8227-4cbd0c814cb4"
}
```

# Response

• Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous job ID. For details, see <b>Asynchronous Job Query</b> .

Example response
 STATUS CODE 200
 "job\_id": "edc89b490d7d4392898e19b2deb34797"
 }

## **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.3.2 Replicating an Image Across Regions

## **Function**

This API is an extension one and is used to replicate a private from one region to another region to create ECSs of the same type. This allows you to migrate services between regions.

This API is an asynchronous one. If **job\_id** is returned, the task is successfully delivered. You need to query the status of the asynchronous task. If the status is **success**, the task is successfully executed. If the status is **failed**, the task fails.

## **Constraints**

- The destination region cannot be the same as the source region.
- Encrypted images do not support cross-region replication.
- The size of each image to be replicated across regions cannot be larger than 128 GB.
- A maximum of five private images can be replicated at a time.
- Private images created using ISO files do not support cross-region replication.

# URI

POST /v1/cloudimages/{image\_id}/cross\_region\_copy

Table 5-15 lists the parameters in the URI.

Table 5-15 Parameter description

Parameter	Mandator y	Туре	Description
image_id	Yes	String	Specifies the image ID.
			For details about how to obtain the image ID, see <b>Querying Images</b> .

# Request

#### • Request parameters

Parameter	Mandator y	Туре	Description
name	Yes	String	Specifies the image name. For detailed description, see Image Attributes.
description	No	String	Provides supplementary information about the image. For detailed description, see Image Attributes. The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed. This parameter is left blank by default.

Parameter	Mandator y	Туре	Description
region	Yes	String	Specifies the ID of the destination region.
			For details about how to obtain region IDs, see section "Listing Regions" in <i>Identity and Access Management API Reference</i> .
project_name	Yes	String	Specifies the name of the project in the destination region.
agency_name	Yes	String	Specifies the agency name.  For details about how to create an IAM agency, see "How Do I Create an IAM Agency?" in <i>Image Management Service User Guide</i> .
vault_id	No	String	Specifies the vault ID. This parameter is mandatory if you are replicating a full-ECS image. You can obtain the vault ID from the CBR console or by referring to "Querying the Vault List" in Cloud Backup and Recovery API Reference.

## • Example request

```
If the image is not a full-ECS image:

POST https://{Endpoint}/v1/cloudimages/465076de-dc36-4aec-80f5-ef9d8009428f/

cross_region_copy
{

    "name":"test-copy-1001-4",
    "description":"region-1",
    "region":"region-1",
    "project_name":"region-1",
    "agency_name":"ims_copy_image"
}
```

If the image is a full-ECS image: POST https://{Endpoint}/v1/cloudimages/465076de-dc36-4aec-80f5-ef9d8009428f/ cross\_region\_copy { "name":"test-copy-1001-4",

```
"description":"test",
"region":"region-1",
"project_name":"region-1",
"agency_name":"ims_copy_image",
"vault_id":"6yhtb5df-1bc3-4c3f-893e-3e4716yhgt61"
}
```

# Response

• Response parameters

Parameter	Туре	Description
job_id	String	Specifies the asynchronous task ID.

```
    Example response
    STATUS CODE 200
{
        "job_id": "edc89b490d7d4392898e19b2deb34797"
}
```

# **Returned Values**

Normal

200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.4 Image Quota

# 5.4.1 Querying the Image Quota

## **Function**

This extension API is used to query the quota of private images of a tenant in the current region.

## **URI**

# GET /v1/cloudimages/quota

# Request

Request parameters

None

• Example request GET https://{Endpoint}/v1/cloudimages/quota

# Response

#### • Response parameters

Parameter	Туре	Description
quotas	Object	Specifies the quota information.
		For details, see <b>Table 5-16</b> .

Table 5-16 Data structure description of the quotas field

Parameter	Туре	Description
resources	Array of objects	Specifies the images included in the quota.  For details, see <b>Table 5-17</b> .

Table 5-17 Data structure description of the quotas.resources field

Parameter	Туре	Description
type	String	Specifies the type of the resource to be queried.
used	Integer	Specifies the used quota.
quota	Integer	Specifies the total quota.
min	Integer	Specifies the minimum quota.
max	Integer	Specifies the maximum quota.

#### • Example response

```
"max": 1000
}
]
}
}
```

# **Returned Values**

- Normal200
- Abnormal

Returned Value	Description
400 Bad Request	Request error. For details, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 5.5 Image Jobs

# 5.5.1 Asynchronous Job Query

# **Function**

This is an extension API. It is used to query for the execution status of an asynchronous job, for example, querying for the execution status of an image exporting job.

## **URI**

GET /v1/{project\_id}/jobs/{job\_id}

Table 5-18 lists the parameters in the URI.

Table 5-18 Parameter description

Parameter	Mandatory	Description
project_id	Yes	Specifies the project ID.
job_id	Yes	Specifies the asynchronous job ID.

# Request

Request parameters None

Example request
 GET /v1/ac234de25c6741d2b1273da49eea1b9e/jobs/ff8080814dbd65d7014dbe0d84db0013

# Response

## • Response parameters

Parameter	Туре	Description
status	String	Specifies the job status. The value can be:
		SUCCESS: The job is successfully executed.
		FAIL: The job failed to be executed.
		RUNNING: The job is in progress.
		• INIT: The job is being initialized.
job_id	String	Specifies the job ID.
job_type	String	Specifies the job type.
begin_time	String	Specifies the start time of the job. The value is in UTC format.
end_time	String	Specifies the end time of the job. The value is in UTC format.
error_code	String	Specifies the error code.
fail_reason	String	Specifies the failure cause.
entities	Object	Specifies the custom attributes of the job.
		If the job status is normal, the image ID will be returned. If the status is abnormal, an error code and details will be returned.
		For details, see <b>Table 5-19</b> .

Table 5-19 Data structure description of the entities field

Parameter	Туре	Description
image_id	String	Specifies the image ID.
current_task	String	Specifies the job name.
image_name	String	Specifies the image name.

Parameter	Туре	Description
process_percent	Double	Specifies the job progress.
results	Array of result objects	Specifies job execution results. For details, see <b>Table 5-20</b> .
sub_jobs_result	Array of SubJobResult objects	Specifies sub-job execution results. For details, see <b>Table 5-21</b> .
sub_jobs_list	Array of string	Specifies the sub-job IDs.

Table 5-20 Data structure description of the result field

Parameter	Туре	Description
image_id	String	Specifies the image ID.
project_id	String	Specifies the project ID.
status	String	Specifies the job status.

Table 5-21 Data structure description of the SubJobResult field

Parameter	Туре	Description
status	String	Specifies the sub-job status. The value can be:
		SUCCESS: The sub-job is successfully executed.
		FAIL: The sub-job failed to be executed.
		• <b>RUNNING</b> : The sub-job is in progress.
		• <b>INIT</b> : The sub-job is being initialized.
job_id	String	Specifies a sub-job ID.
job_type	String	Specifies the sub-job type.
begin_time	String	Specifies the start time of the sub-job. The value is in UTC format.
end_time	String	Specifies the end time of the sub-job. The value is in UTC format.
error_code	String	Specifies the error code.
fail_reason	String	Specifies the failure cause.

Parameter	Туре	Description
entities	Object SubJobEntities	Specifies the custom attributes of the subjob. For details, see <b>Table 5-22</b> .
		If a sub-job is properly executed, an image ID is returned.
		If an exception occurs on the sub-job, an error code and associated information are returned.

Table 5-22 Data structure description of the SubJobEntities field

Parameter	Туре	Description
image_id	String	Specifies the image ID.
image_na me	String	Specifies the image name.

Example response

# **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.

Returned Value	Description
403 Forbidden	You do not have the rights to perform the operation.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6 Native OpenStack APIs

# 6.1 Image (Native OpenStack APIs)

# 6.1.1 Querying Images (Native OpenStack API)

#### **Function**

This API is used to obtain the image list.

This API does not return the complete result at once, but uses pagination.

# **Pagination**

Pagination refers to the function of returning a subset of a group of images, a link to obtain the next set of images, and a link of the set of images. By default, a set contains 25 images. You can also use the **limit** and **marker** parameters to paginate through images manually and specify the number of images that can be returned.

The parameter **first** in the response indicates the URL of the first page of images, and parameter **next** indicates the URL of the next page of images. When the last page of images is queried, there is no parameter **next**.

#### URI

GET /v2/images

#### 

- You can type a question mark (?) and an ampersand (&) at the end of the URI to define multiple search criteria. For details, see the example request.
- If you need the API of the OpenStack Queens release, the request header must contain **X-Api-Version**. If the value of **X-Api-Version** is any letter after **M** in the Alphabet, the API of the Queens release is returned. If the value is **M** or a letter before **M**, the API of the Mitaka release is returned.

Table 6-1 lists the parameters.

Table 6-1 Parameter description

Parameter	Mandatory	Туре	Description
isregistered	No	String	Specifies whether the image is available. The value can be <b>true</b> . The value is <b>true</b> for all extension APIs by default. Common users can query only the images for which the value of this parameter is <b>true</b> .
imagetype	No	String	<ul> <li>Specifies the image type. The following types are supported:</li> <li>Public image: The value is gold.</li> <li>Private image: The value is private.</li> <li>Shared image: The value is shared.</li> </ul>
protected	No	Boolean	Specifies whether the image is protected. The value is <b>true</b> or <b>false</b> . Set it to <b>true</b> when you query public images. This parameter is optional when you query private images.
visibility	No	String	Specifies whether the image is available to other tenants. Available values include:  • public: public image  • private: private image  • shared: shared image
owner	No	String	Specifies the tenant to which the image belongs.
id	No	String	Specifies the image ID.

Parameter	Mandatory	Туре	Description
status	No	String	Specifies the image status. The value can be one of the following:
			• queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.
			saving: indicates that the image file is being uploaded to the backend storage.
			deleted: indicates that the image has been deleted.
			killed: indicates that an error occurs on the image uploading.
			active: indicates that the image is available for use.
name	No	String	Specifies the image name. Exact matching is used. For detailed description, see Image Attributes.
container_for mat	No	String	Specifies the container type. The default value is <b>bare</b> .
disk_format	No	String	Specifies the image format. The value can be zvhd2, vhd, zvhd, raw, iso, or qcow2. The default value is zvhd2 for a non-ISO image.
min_ram	No	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. Generally, the value is <b>0</b> .
min_disk	No	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.
os_bit	No	String	Specifies the OS architecture, 32 bit or 64 bit.

Parameter	Mandatory	Туре	Description
platform	No	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
marker	No	String	Specifies the start number from which images are queried. The value is the image ID.
limit	No	Integer	Specifies the number of images to be queried. The value is an integer. By default, 25 images can be queried.
sort_key	No	String	Specifies the field for sorting the query results. The value can be an attribute of the image: name, container_format, disk_format, status, id, size, or create_at. The default value is create_at.
sort_dir	No	String	Specifies whether the query results are sorted in ascending or descending order. Its value can be <b>desc</b> (default) or <b>asc</b> . This parameter is used together with parameter <b>sort_key</b> . The default value is <b>desc</b> .
os_type	No	String	Specifies the image OS type. The value can be <b>Linux</b> , <b>Windows</b> , or <b>Other</b> .
tag	No	String	Specifies a tag added to an image. Tags can be used as a filter to query images.  NOTE  The tagging function has been upgraded. If the tags added before the function upgrade are in the format of "Key.Value", query tags using "Key=Value". For example, an existing tag is a.b. After the tag function upgrade, query the tag using "tag=a=b".

Parameter	Mandatory	Туре	Description
member_statu s	No	String	Specifies the member status. The value can be accepted, rejected, or pending. accepted: indicates that the shared image is accepted. rejected indicates that the image shared by others is rejected. pending indicates that the image shared by others needs to be confirmed. To use this parameter, set visibility to shared during the query.
support_kvm	No	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xen	No	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_larg ememory	No	String	Specifies whether the image supports large-memory ECSs. If the image supports large-memory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required. For details about the image OSs supported by large-memory ECSs, see <b>Table 9-4</b> .
support_disk intensive	No	String	Specifies whether the image supports disk-intensive ECSs. If the image supports disk-intensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required. For details about the image OSs supported by disk-intensive ECSs, see <b>Table 9-4</b> .
support_hig hperformance	No	String	Specifies whether the image supports high-performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required. For details about the image OSs supported by high-performance computing ECSs, see <b>Table 9-4</b> .

Parameter	Mandatory	Туре	Description
support_xen _gpu_type	No	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. For details about the image OSs supported by GPU-accelerated ECSs, see Table 9-2. If the image does not support GPU-accelerated ECSs on the Xen platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_kvm _gpu_type	No	String	Specifies whether the image supports GPU-accelerated ECSs on the KVM platform. See Table 9-3 for its value. If the image does not support GPU-accelerated ECSs on the KVM platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_xen _hana	No	String	Specifies whether the image supports HANA ECSs on the Xen platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_kvm _infiniband	No	String	Specifies whether the image supports ECSs with the InfiniBand NIC on the KVM platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This attribute cannot co-exist withsupport_xen.

Parameter	Mandatory	Туре	Description
created_at	No	String	Specifies the time when the image was created. Images can be queried by time. The value is in the format of <i>Operator:UTC time</i> .
			The following operators are supported:
			• gt: greater than
			gte: greater than or equal to
			It: less than
			Ite: less than or equal to
			• eq: equal to
			neq: not equal to
			The time format is <i>yyyy-MM-ddThh:mm:ssZ</i> or <i>yyyy-MM-ddh:mm:ss</i> .
			For example, to query images created before Oct 28, 2018 10:00:00, set the value of created_at to lt: 2018-10-28T10:00:00Z.
updated_at	No	String	Specifies the time when the image was modified. Images can be queried by time. The value is in the format of <i>Operator:UTC time</i> .
			The following operators are supported:
			• gt: greater than
			gte: greater than or equal to
			It: less than
			Ite: less than or equal to
			• eq: equal to
			neq: not equal to
			The time format is <i>yyyy-MM-ddThh:mm:ssZ</i> or <i>yyyy-MM-dd hh:mm:ss</i> .
			For example, to query images updated before Oct 28, 2018 10:00:00, set the value of updated_at to lt: 2018-10-28T10:00:00Z.

# **Common Query Methods**

Public imagesGET /v2/images?\_\_imagetype=gold&visibility=public&protected=true

Private images

GET /v2/images?owner={project\_id}

• Available shared images

GET /v2/images? member\_status=accepted&visibility=shared&\_\_imagetype=shared

• Rejected images

GET /v2/images? member\_status=rejected&visibility=shared&\_\_imagetype=shared

Unaccepted images

GET /v2/images? member\_status=pending&visibility=shared&\_\_imagetype=shared

# Request

• Request parameters

None

Example request GET https://{Endpoint}/v2/images

# Response

Response parameters

Parameter	Туре	Description
first	String	Specifies the URL of the first page of images.
next	String	Specifies the URL of the next page of images. When the last page of images is queried, there is no parameter <b>next</b> .
schema	String	Specifies the URL for the schema describing a list of images.
images	Array of objects	Specifies the resource type. For details, see <b>Table 6-2</b> .

Table 6-2 Data structure description of the images field

Parameter	Туре	Description
backup_id	String	Specifies the backup ID. If the image is created from a backup, set the value to the backup ID. Otherwise, this parameter is not required.
data_origin	String	Specifies the image source. If the image is a public image, the value is left empty.
description	String	Specifies the image description.
image_location	String	Specifies the location where the image is stored.
image_size	String	Specifies the size (bytes) of the image file. The value is greater than 0.
image_source_type	String	Specifies the backend storage of the image. Only UDS is supported currently.
is_config_init	String	Specifies whether initial configuration is complete. The value can be <b>true</b> or <b>false</b> .
isregistered	String	Specifies whether the image is available. The value can be <b>true</b> . The value is <b>true</b> for all extension APIs by default. Common users can query only the images for which the value of this parameter is <b>true</b> .
lazyloading	String	Specifies whether the image supports lazy loading. The value can be <b>true</b> , <b>false</b> , <b>True</b> , or <b>False</b> .
_originalimagename	String	Specifies the parent image ID. If the image is a public image or created from an image file, the value is left empty.

Parameter	Туре	Description
imagetype	String	<ul> <li>Specifies the image type. The following types are supported:</li> <li>Public image: The value is gold.</li> <li>Private image: The value is private.</li> <li>Shared image: The value is shared.</li> </ul>
protected	Boolean	Specifies whether the image is protected. Set it to <b>true</b> when you query public images. This parameter is optional when you query private images.
virtual_env_type	String	Specifies the environment where the image is used. The value can be FusionCompute, Ironic, DataImage, or IsoImage.
		For an ECS image (system disk image), the value is     FusionCompute.
		For a data disk image, the value is <b>DataImage</b> .
		• For a BMS image, the value is <b>Ironic</b> .
		For an ISO image, the value is <b>IsoImage</b> .
virtual_size	Integer	This parameter is unavailable currently.
visibility	String	Specifies whether the image is available to other tenants. The value can be one of the following:  • public: public image  • private: private image  • shared: shared image
owner	String	Specifies the tenant to which the image belongs.
id	String	Specifies the image ID.

Parameter	Туре	Description
status	String	Specifies the image status. The value can be one of the following:
		• queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.
		saving: indicates that the image file is being uploaded to the backend storage.
		deleted: indicates that the image has been deleted.
		killed: indicates that an error occurs on the image uploading.
		active: indicates that the image is available for use.
name	String	Specifies the image name. For detailed description, see Image Attributes.
container_format	String	Specifies the container type.
disk_format	String	Specifies the image format. The value can be zvhd2, vhd, zvhd, raw, iso, or qcow2. The default value is zvhd2 for a non-ISO image.
min_ram	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. Generally, the value is <b>0</b> .
max_ram	String	Specifies the maximum memory (MB) of the image.
min_disk	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.
os_bit	String	Specifies the OS architecture, 32 bit or 64 bit.

Parameter	Туре	Description
os_feature_list	String	Specifies additional attributes of the image. The value is a list (in JSON format) of advanced features supported by the image.
platform	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
schema	String	Specifies the image schema.
self	String	Specifies the image URL.
size	Integer	This parameter is unavailable currently.
os_type	String	Specifies the image OS type. The value can be <b>Linux</b> , <b>Windows</b> , or <b>Other</b> .
os_version	String	Specifies the OS version.
tags	Array of strings	Specifies tags of the image, through which you can manage private images in your own way.
support_kvm	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xen	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_largememory	String	Specifies whether the image supports large-memory ECSs. If the image supports large-memory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required. For details about the image OSs supported by large-memory ECSs, see <b>Table 9-4</b> .

Parameter	Туре	Description
support_diskintensive	String	Specifies whether the image supports disk-intensive ECSs. If the image supports disk-intensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required. For details about the image OSs supported by disk-intensive ECSs, see <b>Table 9-4</b> .
support_highperformance	String	Specifies whether the image supports high-performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required. For details about the image OSs supported by high-performance computing ECSs, see <b>Table 9-4</b> .
support_xen_gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. For details about the image OSs supported by GPU-accelerated ECSs, see Table 9-2. If the image does not support GPU-accelerated ECSs on the Xen platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_kvm_gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the KVM platform. See Table 9-3 for its value. If the image does not support GPU-accelerated ECSs on the KVM platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.

Parameter	Туре	Description
support_xen_hana	String	Specifies whether the image supports HANA ECSs on the Xen platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_kvm_infiniband	String	Specifies whether the image supports ECSs with the InfiniBand NIC on the KVM platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This attribute cannot co-exist withsupport_xen.
root_origin	String	Specifies that the image is created from an external image file. Value: <b>file</b>
sequence_num	String	Specifies the ECS system disk slot number corresponding to the image.  Example value: <b>0</b>
support_fc_inject	String	Specifies whether the image supports password/private key injection using Cloud-Init.  If the value is set to <b>true</b> , password/private key injection using Cloud-Init is not supported.  NOTE  This parameter is valid only for ECS system disk images.
created_at	String	Specifies the time when the image was created. The value is in UTC format.
updated_at	String	Specifies the time when the image was updated. The value is in UTC format.
active_at	String	Specifies the time when the image status became <b>active</b> .
checksum	String	This parameter is unavailable currently.

Parameter	Туре	Description
hw_firmware_type	String	Specifies the ECS boot mode. Available values include:  • bios indicates the BIOS boot mode.
		uefi indicates the UEFI     boot mode.
file	String	Specifies the URL for uploading and downloading the image file.
support_amd	String	Specifies whether the image uses AMD's x86 architecture. The value can be <b>true</b> or <b>false</b> .
systemcmkid	String	Specifies the ID of the key used to encrypt the image.
hw_vif_multiqueue_enabled	String	Specifies whether the image supports NIC multi-queue. The value can be <b>true</b> or <b>false</b> .

#### • Example response

```
STATUS CODE 200
 "schema": "/v2/schemas/images",
"next": "/v2/images?__isregistered=true&marker=0328c25e-c840-4496-81ac-c4e01b214b1f&__imagetype=gold&limit=2",
 "images": [
  "created_at": "2018-09-06T14:03:27Z",
"_image_source_type": "uds",
    "container_format": "bare",
    "file": "/v2/images/bc6bed6e-ba3a-4447-afcc-449174a3eb52/file",
    "updated_at": "2018-09-06T15:17:33Z",
    "protected": true,
    "checksum": "d41d8cd98f00b204e9800998ecf8427e",
    "id": "bc6bed6e-ba3a-4447-afcc-449174a3eb52",
    "_isregistered": "true",
    "min_ram": 2048,
    "__lazyloading": "true",
    "owner": "1bed856811654c1cb661a6ca845ebc77",
    "_os_type": "Linux",
"_imagetype": "gold",
    "visibility": "public",
    "virtual_env_type": "FusionCompute",
    "tags": [],
    "_platform": "CentOS",
    "size": 0,
    "_os_bit": "64",
"_os_version": "CentOS 7.3 64bit",
    "name": "CentOS 7.3 64bit vivado",
"self": "/v2/images/bc6bed6e-ba3a-4447-afcc-449174a3eb52",
    "disk_format": "zvhd2",
    "virtual_size": null,
    "hw_firmware_type": "bios",
```

```
"status": "active"
   "schema": "/v2/schemas/image",
"min_disk": 100,
   "created_at": "2018-09-06T14:03:05Z",
   "__image_source_type": "uds",
   "container_format": "bare",
"file": "/v2/images/0328c25e-c840-4496-81ac-c4e01b214b1f/file",
   "updated_at": "2018-09-25T14:27:40Z",
   "protected": true,
"checksum": "d41d8cd98f00b204e9800998ecf8427e",
   "id": "0328c25e-c840-4496-81ac-c4e01b214b1f",
   "__isregistered": "true",
   "min_ram": 2048,
   "__lazyloading": "true",
   "owner": "1bed856811654c1cb661a6ca845ebc77",
  "_os_type": "Linux",
"_imagetype": "gold",
"visibility": "public",
   "virtual_env_type": "FusionCompute",
   "tags": [],
"__platform": "CentOS",
   "size": 0,
  "__os_bit": "64",
"__os_version": "CentOS 7.3 64bit",
   "name": "CentOS 7.3 64bit with sdx",
   "self": "/v2/images/0328c25e-c840-4496-81ac-c4e01b214b1f",
   "disk_format": "zvhd2",
"virtual_size": null,
   "hw_firmware_type": "bios",
   "status": "active"
"first": "/v2/images?__isregistered=true&__imagetype=gold&limit=2"
```

## **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error. For details about the returned error code, see <b>Error Codes</b> .
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.1.2 Querying Image Details (Native OpenStack API)

# **Function**

This API is used to query details about a public or private image.

## **URI**

GET /v2/images/{image\_id}

**Table 6-3** lists the parameters.

Table 6-3 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.

# Request

• Request parameters

None

• Example request GET https://{Endpoint}/v2/images/33ad552d-1149-471c-8190-ff6776174a00

# Response

Response parameters

Parameter	Туре	Description
file	String	Specifies the URL for uploading and downloading the image file.
owner	String	Specifies the tenant to which the image belongs.
id	String	Specifies the image ID.
size	Long	This parameter is unavailable currently.
self	String	Specifies the image URL.
schema	String	Specifies the image schema.

Parameter	Туре	Description
status	String	Specifies the image status. The value can be one of the following:
		• queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.
		saving: indicates that the image file is being uploaded to the backend storage.
		deleted: indicates that the image has been deleted.
		killed: indicates that an error occurs on the image uploading.
		active: indicates that the image is available for use.
tags	Array of strings	Specifies tags of the image, through which you can manage private images in your own way. You can use the image tag API to add different tags to each image and filter images by tag.
visibility	String	Specifies whether the image is available to other tenants. Available values include:
		<ul><li> private: private image</li><li> public: public image</li><li> shared: shared image</li></ul>
name	String	Specifies the image name. For detailed description, see Image Attributes.
checksum	String	This parameter is unavailable currently.

Parameter	Туре	Description
protected	Boolean	Specifies whether the image is protected. A protected image cannot be deleted. The value can be <b>true</b> or <b>false</b> .
container_format	String	Specifies the container type.
min_ram	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. Generally, the value is <b>0</b> .
max_ram	String	Specifies the maximum memory (MB) of the image. You can set this parameter based on the ECS specifications. Generally, you do not need to set this parameter.
updated_at	String	Specifies the time when the image was updated. The value is in UTC format.
os_bit	String	Specifies the OS architecture, 32 bit or 64 bit.
os_version	String	Specifies the OS version.
description	String	Specifies the image description. For detailed description, see Image Attributes.
disk_format	String	Specifies the image format. The value can be zvhd2, vhd, zvhd, raw, iso, or qcow2. The default value is zvhd2 for a non-ISO image.
isregistered	String	Specifies whether the image has been registered. The value can be <b>true</b> or <b>false</b> .

Parameter	Туре	Description
platform	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
os_type	String	Specifies the OS type. The value can be <b>Linux</b> , <b>Windows</b> , or <b>Other</b> .
systemcmkid	String	Specifies the ID of the key used to encrypt the image.
min_disk	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.
virtual_env_type	String	Specifies the environment where the image is used. The value can be FusionCompute, Ironic, Datalmage, or Isolmage.
		<ul> <li>For an ECS image (system disk image), the value is</li> <li>FusionCompute.</li> </ul>
		For a data disk image, the value is     DataImage.
		For a BMS image, the value is <b>Ironic</b> .
		For an ISO image, the value is IsoImage.
image_source_type	String	Specifies the backend storage of the image. Only UDS is supported currently.

Parameter	Туре	Description
imagetype	String	Specifies the image type. The following types are supported:
		<ul> <li>Public image: The value is gold.</li> </ul>
		<ul> <li>Private image: The value is private.</li> </ul>
		Shared image: The value is <b>shared</b> .
created_at	String	Specifies the time when the image was created. The value is in UTC format.
virtual_size	Integer	This parameter is unavailable currently.
originalimagename	String	Specifies the parent image ID.
		If the image is a public image or created from an image file, this value is left empty.
backup_id	String	Specifies the backup ID. To create an image using a backup, set the value to the backup ID. Otherwise, this value is left empty.
image_size	String	Specifies the size (bytes) of the image file. The value is greater than 0.
data_origin	String	Specifies the image source.
		If the image is a public image, this parameter is left empty.
root_origin	String	Specifies that the image is created from an external image file. Value: <b>file</b>
lazyloading	String	Specifies whether the image supports lazy loading. The value can be true, false, True, or False.

Parameter	Туре	Description
active_at	String	Specifies the time when the image status became active.
os_feature_list	String	Specifies additional attributes of the image. The value is a list (in JSON format) of advanced features supported by the image.
sequence_num	String	This parameter is unavailable currently.
support_kvm	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xen	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_largememory	String	Specifies whether the image supports largememory ECSs. If the image supports largememory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required. For the supported OSs, see <b>Table 9-4</b> .
support_diskintensive	String	Specifies whether the image supports diskintensive ECSs. If the image supports diskintensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_highperformanc e	String	Specifies whether the image supports high-performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.

Parameter	Туре	Description
support_xen_gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. See Table 9-2 for its value. If the image does not support GPU-accelerated ECSs on the Xen platform, this parameter is not required. This parameter cannot co-exist withsupport_xen andsupport_kvm.
support_kvm_gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the KVM platform. See <b>Table 9-3</b> for its value.  If the image does not support GPU-accelerated ECSs on the KVM platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.
support_xen_hana	String	Specifies whether the image supports HANA ECSs on the Xen platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This attribute cannot coexist withsupport_xen andsupport_kvm.
support_kvm_infiniband	String	Specifies whether the image supports ECSs with the InfiniBand NIC on the KVM platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This attribute cannot coexist withsupport_xen.

Parameter	Туре	Description
support_fc_inject	String	Specifies whether the image supports password/ private key injection using Cloud-Init. The parameter value can be <b>true</b> or <b>false</b> .  If the value is set to <b>true</b> , password/private key injection using Cloud-Init is not supported.
		NOTE  This parameter is valid only for ECS system disk images.
hw_firmware_type	String	Specifies the ECS boot mode. Available values include:  • bios indicates the BIOS
		<ul> <li>boot mode.</li> <li>uefi indicates the UEFI boot mode.</li> </ul>
hw_vif_multiqueue_enable d	String	Specifies whether the image supports NIC multi-queue. The value can be <b>true</b> or <b>false</b> .
image_location	String	Specifies the location where the image is stored.
is_config_init	String	Specifies whether initial configuration is complete. The value can be <b>true</b> or <b>false</b> .
support_amd	String	Specifies whether the image uses AMD's x86 architecture. The value can be <b>true</b> or <b>false</b> .

#### Example response

```
STATUS CODE 200

{
    "schema": "/v2/schemas/image",
    "min_disk": 100,
    "created_at": "2018-09-06T14:03:27Z",
    "__image_source_type": "uds",
    "container_format": "bare",
    "file": "/v2/images/bc6bed6e-ba3a-4447-afcc-449174a3eb52/file",
    "updated_at": "2018-09-06T15:17:33Z",
    "protected": true,
    "checksum": "d41d8cd98f00b204e9800998ecf8427e",
```

```
"id": "bc6bed6e-ba3a-4447-afcc-449174a3eb52",
"__isregistered": "true",
"min_ram": 2048,
"_lazyloading": "true",
"owner": "1bed856811654c1cb661a6ca845ebc77",
"_os_type": "Linux",
"_imagetype": "gold",
"visibility": "public",
"virtual_env_type": "FusionCompute",
"tags": [],
"__platform": "CentOS",
"size": 0,
"__os_bit": "64",
"_os_version": "CentOS 7.3 64bit",
"name": "CentOS 7.3 64bit vivado",
"self": "/v2/images/bc6bed6e-ba3a-4447-afcc-449174a3eb52",
"disk_format": "zvhd2",
"virtual_size": null,
"status": "active"
```

#### **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.

The service is unavailable.

# 6.1.3 Updating Image Information (Native OpenStack API)

#### **Function**

This API is used to modify image information.

503 Service Unavailable

#### **Constraints**

Only customized attributes, image name, and image description can be modified.

#### **URI**

PATCH /v2/images/{image\_id}

**Table 6-4** lists the parameters.

Table 6-4 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.
			For details about how to obtain the image ID, see <b>Querying Images</b> .

# Request

#### Request parameters

Glance has two methods of updating image information. The method is specified by **Content-Type** in the HTTP header. **application/openstack-images-v2.0-json-patch** and **application/openstack-images-v2.1-json-patch** are supported. Content types differ only in the format of the request message body.

**Table 6-5** v2.1 request message body

Paramete r	Mandator y	Туре	Description
[Array]	Yes	Array of objects	For details, see <b>Table 6-6</b> .

Table 6-6 Data structure description of the [Array] field

Parameter	Туре	Mandatory	Description
ор	String	Yes	Indicates the type of the update operation, including replacing, adding, and deleting an attribute.  The value can be <b>replace</b> ,
			add, or remove.

Parameter	Туре	Mandatory	Description
path	String	Yes	Indicates the name of the target attribute.
			For <b>replace</b> and <b>remove</b> , the value can only be an existing attribute of the image. For <b>add</b> , the value can be an existing or a new attribute. If the value is an existing attribute, <b>add</b> takes the same effect as <b>replace</b> . If the value is a new attribute, the <b>add</b> operation is performed. Add a slash (/) before the attribute name.
value	String	No	Indicates the value of the attribute to be updated or added.
			Mandatory for <b>replace</b> and <b>add</b> , and not for <b>remove</b>

Table 6-7 v2.0 request message body

Paramete r	Mandator y	Туре	Description
[Array]	Yes	Array of objects	For details, see <b>Table 6-8</b> .

Table 6-8 Data structure description of the [Array] field

Parameter	Туре	Mandatory	Description
replace	String	Mandatory for any of the three values	Indicates that an image attribute will be replaced. The value is the attribute to be replaced and a slash (/) must be added in front of the attribute name.
add	String		Indicates that an image attribute will be added. The value is the attribute to be added and a slash (/) must be added in front of the attribute name.

Parameter	Туре	Mandatory	Description
remove	String		Indicates that an image attribute will be deleted. The value is the attribute to be deleted and a slash (/) must be added in front of the attribute name.
value	String	Mandatory for replace and add, and not for remove	Indicates the value of the attribute to be updated or added. For detailed description, see Image Attributes.

#### Example request

PATCH https://{Endpoint}/v2/images/33ad552d-1149-471c-8190-ff6776174a00

```
v2.1 request body
"Content-Type:application/openstack-images-v2.1-json-patch"
         "op": "replace",
"path": "/name",
"value": "test01"
    }
```

```
v2.0 request body "Content-Type:application/openstack-images-v2.0-json-patch"
        "replace": "/name",
"value": "test01"
    }
]
```

# Response

#### Response parameters

Parameter	Туре	Description
file	String	Specifies the URL for uploading and downloading the image file.
owner	String	Specifies the tenant to which the image belongs.
id	String	Specifies the image ID.
size	Long	This parameter is unavailable currently.
self	String	Specifies the image URL.
schema	String	Specifies the image schema.

Parameter	Туре	Description
status	String	Specifies the image status. The value can be:
		queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.
		• saving: indicates that the image file is being uploaded to the backend storage.
		deleted: indicates that the image has been deleted.
		killed: indicates that an error occurs on the image uploading.
		active: indicates that the image is available for use.
tags	Array of strings	Specifies tags of the image, through which you can manage private images in your own way. You can use the image tag API to add different tags to each image and filter images by tag.
visibility	String	Specifies whether the image is available to other tenants. The value can be:
		private: private image
		• <b>public</b> : public image
		shared: shared image
name	String	Specifies the image name. For detailed description, see Image Attributes.
checksum	String	This parameter is unavailable currently.
protected	Boolean	Specifies whether the image is protected. A protected image cannot be deleted. The value can be <b>true</b> or <b>false</b> .
container_form at	String	Specifies the container type.
min_ram	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. The default value is <b>0</b> .

Parameter	Туре	Description
max_ram	String	Specifies the maximum memory (MB) of the image. The parameter value depends on the ECS specifications and is not configured by default.
updated_at	String	Specifies the time when the image was updated. The value is in UTC format.
os_bit	String	Specifies the OS architecture, 32 bit or 64 bit.
os_version	String	Specifies the OS version.
description	String	Specifies the image description. For detailed description, see Image Attributes.
disk_format	String	Specifies the image format. The value can be <b>zvhd2</b> , <b>vhd</b> , <b>zvhd</b> , <b>raw</b> , <b>iso</b> , or <b>qcow2</b> . The default value is <b>zvhd2</b> for a non-ISO image.
isregistered	String	Specifies whether the image has been registered. The value can be <b>true</b> or <b>false</b> .
platform	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
os_type	String	Specifies the OS type. The value can be <b>Linux</b> , <b>Windows</b> , or <b>Other</b> .
systemcmki d	String	Specifies the ID of the key used to encrypt the image.
min_disk	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.

Parameter	Туре	Description	
virtual_env_type	String	Specifies the environment where the image is used. The value can be <b>FusionCompute</b> , <b>Ironic</b> , <b>DataImage</b> , or <b>IsoImage</b> .	
		<ul> <li>For an ECS image (system disk image), the value is FusionCompute.</li> </ul>	
		<ul> <li>For a data disk image, the value is DataImage.</li> </ul>	
		For a BMS image, the value is Ironic.	
		For an ISO image, the value is IsoImage.	
image_source _type	String	Specifies the backend storage of the image. Only UDS is supported currently.	
imagetype	String	Specifies the image type. The following types are supported:	
		Public image: The value is <b>gold</b> .	
		<ul><li>Private image: The value is private.</li><li>Shared image: The value is shared.</li></ul>	
created_at	String	Specifies the time when the image was created. The value is in UTC format.	
virtual_size	Integer	This parameter is unavailable currently.	
originalimage name	String	Specifies the parent image ID.  If the image is a public image or created from an image file, the value is left empty.	
backup_id	String	Specifies the backup ID. If the image is created from a backup, set the value to the backup ID. Otherwise, this parameter is not required.	
image_size	String	Specifies the size (bytes) of the image file. The value must be greater than <b>0</b> .	
data_origin	String	Specifies the image source.	
		If the image is a public image, the value is left empty.	

Parameter	Туре	Description	
root_origin	String	Specifies that the image is created from an external image file. Value: file	
lazyloading	String	Specifies whether the image supports lazy loading. The value can be <b>true</b> , <b>false</b> , <b>True</b> , or <b>False</b> .	
active_at	String	Specifies the time when the image status became <b>active</b> .	
os_feature_list	String	Specifies additional attributes of the image. The value is a list (in JSON format) of advanced features supported by the image.	
account_code	String	Specifies the charging identifier for the image.	
hw_firmware_ty pe	String	Specifies the ECS boot mode. The value can be:  • bios indicates the BIOS boot mode. This value will be used by fault if this parameter does not exist in the response.  • uefi indicates the UEFI boot mode.	
hw_vif_multiqu eue_enabled	String	Specifies whether the image supports NIC multi-queue. The value can be true or false.	
support_kvm	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.	
support_xen	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.	
support_large memory	String	Specifies whether the image can be used to create large-memory ECSs. If the image supports large-memory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.  For the supported OSs, see <b>Table 9-4</b> .	

Parameter	Туре	Description
support_diski ntensive	String	Specifies whether the image can be used to create disk-intensive ECSs. If the image supports disk-intensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_highp erformance	String	Specifies whether the image can be used to create high-performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xen_ gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. See <b>Table 9-2</b> for its value. If the image does not support GPU-accelerated ECSs on the Xen platform, this parameter is not required. This parameter cannot co-exist withsupport_xen andsupport_kvm.
support_kvm_ gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the KVM platform. See <b>Table 9-3</b> for its value. If the image does not support GPU-accelerated ECSs on the KVM platform, this parameter is not required. This parameter cannot coexist withsupport_xen andsupport_kvm.
support_xen_ hana	String	Specifies whether the image supports HANA ECSs on the Xen platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This parameter cannot co-exist withsupport_xen andsupport_kvm.
support_kvm_ infiniband	String	Specifies whether the image supports ECSs with the InfiniBand NIC on the KVM platform. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.  This parameter cannot co-exist withsupport_xen.
sequence_nu m	String	Specifies the ECS system disk slot number corresponding to the image. This parameter is unavailable currently.

Parameter	Туре	Description	
support_fc_inj ect	String	Specifies whether the image supports password/private key injection using Cloud-Init.	
		If the value is set to <b>true</b> , password/ private key injection using Cloud-Init is not supported.	
		NOTE  This parameter is valid only for ECS system disk images.	
image_locatio n	String	Specifies the location where the image is stored.	
is_config_init	String	Specifies whether initial configuration is complete. The value can be <b>true</b> or <b>false</b> .	
support_amd	String	Specifies whether the image uses AMD's x86 architecture. The value can be <b>true</b> or <b>false</b> .	

Parameter	Туре	Description
support_agent _list	String	Specifies the agents configured for the image.
		<ul> <li>hss: The Host Security Service         (HSS) agent is configured for the         image.         Host Security Service (HSS) is         designed to improve the overall         security for ECSs. It helps you         identify and manage the         information on your ECSs,         eliminate risks, and defend against         intrusions and web page         tampering.</li> </ul>
		• ces: The host monitoring agent is configured for the image.  Monitoring is key for ensuring ECS performance, reliability, and availability. Using monitored data, you can determine ECS resource utilization. The cloud platform provides Cloud Eye to help you obtain the running statuses of your ECSs. You can use Cloud Eye to automatically monitor ECSs in real time and manage alarms and notifications to keep track of ECS performance metrics.
		Example:
		"support_agent_list": "hss,ces"
		NOTE  If the response does not contain this field, the HSS and host monitoring agents are not configured for the image.

#### • Example response

```
STATUS CODE 200

{
    "file": "/v2/images/33ad552d-1149-471c-8190-ff6776174a00/file",
    "owner": "0b1e494e2660441a957313163095fe5c",
    "id": "33ad552d-1149-471c-8190-ff6776174a00",
    "size": 2,
    "self": "/v2/images/33ad552d-1149-471c-8190-ff6776174a00",
    "schema": "/v2/schemas/image",
    "status": "active",
    "tags": [],
    "visibility": "private",
    "name": "ims_test",
    "checksum": "99914b932bd37a50b983c5e7c90ae93b",
    "protected": false,
    "container_format": "bare",
    "min_ram": 0,
    "updated_at": "2015-12-08T02:30:49Z",
    "__os_bit": "64",
```

```
"_os_version": "Ubuntu 14.04 server 64bit",

"_description": "ims test",

"disk_format": "vhd",

"_isregistered": "true",

"_platform": "Ubuntu",

"_os_type": "Linux",

"min_disk": 40,

"virtual_env_type": "FusionCompute",

"_image_source_type": "uds",

"_imagetype": "private",

"created_at": "2015-12-04T09:45:33Z",

"virtual_size": 0,

"_originalimagename": "33ad552d-1149-471c-8190-ff6776174a00",

"_backup_id": "",

"_productcode": "",

"_image_size": "449261568",

"_data_origin": null,

"hw_firmware_type":"bios"
```

#### **Returned Values**

Normal200

Abnormal

Returned Value	Description	
400 Bad Request	Request error. For details, see Error Codes.	
401 Unauthorized	Authentication failed.	
403 Forbidden	You do not have the rights to perform the operation.	
404 Not Found	The requested resource was not found.	
500 Internal Server Error	Internal service error.	
503 Service Unavailable	The service is unavailable.	

# 6.1.4 Uploading an Image (Native OpenStack API)

#### **Function**

This API is used to upload a local image to the cloud platform. The image to be uploaded must be smaller than 2 GB. To upload an image larger than 2 GB, see **Registering an Image**.

For more information about how to use external files to create images, see sections "Creating a Private Windows Image Using an External Image File" and "Creating a Private Linux Image Using an External Image File" in *Image Management Service User Guide*.

The following describes how to use this API:

1. Prepare the image to be uploaded. The image can be in QCOW2, VMDK, VHD, RAW, VHDX, QED, VDI, QCOW, ZVHD2, or ZVHD format.

- Create metadata for the image by performing the operations in Creating Image Metadata (Native OpenStack API). After the API is invoked successfully, save the image ID.
- 3. Upload the image file with the image ID obtained in 2.

#### URI

PUT /v2/images/{image\_id}/file

Table 6-9 lists the parameters in the URI.

Table 6-9 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.
			image_id is the ID of the image you created by invoking the API for creating image metadata. Image upload may fail if you use other image IDs.
			After this API is invoked, you can check the image status with the image ID. When the image status changes to active, the image is uploaded successfully.

#### Request

Request parameters

Paramete r	Mandato ry	Туре	Description
image_file	Yes	file	Specifies the local file to be uploaded.

• Example request

PUT https://{Endpoint}/v2/images/84ac7f2b-bf19-4efb-86a0-b5be8771b476/file

#### **Ⅲ** NOTE

If you use the curl command to call the API, the example request is as follows: curl -i --insecure 'https://IP/v2/images/84ac7f2b-bf19-4efb-86a0-b5be8771b476/file' -X PUT -H "X-Auth-Token: \$mytoken" -H "Content-Type:application/octet-stream" -T /mnt/userdisk/images/suse.zvhd

#### Response

• Response parameters None

• Example response HTTP/1.1 204

#### **Returned Values**

Normal204

Abnormal

Returned Value	Description	
400 Bad Request	Request error. For details, see Error Codes.	
401 Unauthorized	Authentication failed.	
403 Forbidden	You do not have the rights to perform the operation.	
404 Not Found	The requested resource was not found.	
409 Conflict	Request conflict.	
500 System Error	System error.	

# 6.1.5 Deleting an Image (Native OpenStack API)

#### **Function**

This API is used to delete a private image. You can only delete your own private images.

#### URI

DELETE /v2/images/{image\_id}

Table 6-10 lists the parameters in the URI.

Table 6-10 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.

## Request

• Request parameters

Parameter	Mandator y	Туре	Description
delete_backup	No	Boolean	Specifies whether to delete the CBR backups associated with a full-ECS image when the image is deleted. The value can be true or false.
			• <b>true</b> : When a full-ECS image is deleted, its CBR backups are also deleted.
			false: When a full-ECS image is deleted, its CBR backups are not deleted.

Example request
DELETE https://{Endpoint}/v2/images/4ca46bf1-5c61-48ff-b4f3-0ad4e5e3ba90

"delete\_backup": true

## Response

Response parameters

None

• Example response STATUS CODE 204

#### **Returned Values**

Normal204

Abnormal

Returned Value	Description	
400 Bad Request	Request error.	
401 Unauthorized	Authentication failed.	
403 Forbidden	You do not have the rights to perform the operation.	
404 Not Found	The requested resource was not found.	
500 Internal Server Error	Internal service error.	
503 Service Unavailable	The service is unavailable.	

# 6.1.6 Creating Image Metadata (Native OpenStack API)

## **Function**

This API is used to create image metadata.

After the API is successfully invoked, the image metadata is created, but the image file does not exist yet.

#### **URI**

POST /v2/images

## Request

#### • Request parameters

Parameter	Mandatory	Туре	Description
os_version	No	String	Specifies the image OS version. For the value range, see Values of Related Parameters.
			If this parameter is not specified, the value Other Linux(64 bit) will be used. In that case, the ECS creation using this image may fail, and the ECS created using this image may fail to run properly.
visibility	No	String	Specifies whether the image is available to other tenants.
			The default value is private. When creating image metadata, the value of visibility can be set to private only.

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the image name. If this parameter is not specified, its value is empty by default. In that case, ECS creation using this image will fail. The name contains 1 to 255 characters. For detailed description, see Image Attributes. This parameter is left blank by default.
protected	No	Boolean	Specifies whether the image is protected. A protected image cannot be deleted. The default value is false.
container_format	No	String	Specifies the container format. The default value is bare.
disk_format	No	String	Specifies the image format. The value can be zvhd2, vhd, zvhd, raw, iso, or qcow2. The default value is zvhd2 for a non-ISO image.
tags	No	Array of strings	Lists the image tags. The tag contains 1 to 255 characters. The value is left blank by default.
min_ram	No	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on ECS specifications. The default value is <b>0</b> .

Parameter	Mandatory	Туре	Description
min_disk	No	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB.
			The value of this parameter must be greater than the image system disk capacity. Otherwise, the ECS creation may fail.

#### **MOTE**

Parameters in the request body are strings of no more than 255 characters, and their values can be left blank. Example:

"key": "value"

#### • Example request

```
POST https://{Endpoint}/v2/images

{
    "__os_version": "Ubuntu 14.04 server 64bit",
    "container_format": "bare",
    "disk_format": "vhd",
    "min_disk": 1,
    "min_ram": 1024,
    "name": "test",
    "tags": [
        "test",
        "image"
    ],
    "visibility": "private",
    "protected": false
}
```

## Response

#### • Response parameters

Parameter	Туре	Description
visibility	String	Specifies whether the image is available to other tenants. The value is <b>private</b> .

Parameter	Туре	Description
name	String	Specifies the image name. If this parameter is not specified, its value is empty by default. In that case, ECS creation using this image will fail. The name contains 1 to 128 characters. For detailed description, see Image Attributes.
protected	Boolean	Specifies whether the image is protected. A protected image cannot be deleted. The value is <b>false</b> .
container_format	String	Specifies the container format. The value is <b>bare</b> .
disk_format	String	Specifies the image format. The value can be zvhd2, vhd, zvhd, raw, iso, or qcow2. The default value is zvhd2 for a non-ISO image.
tags	Array of strings	Lists the image tags. The tag contains 1 to 255 characters.
min_ram	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications limit. The value is generally set to <b>0</b> .
min_disk	Integer	Specifies the minimum disk space (GB) required for running the image. The value ranges from 40 GB to 255 GB. It must be greater than the system disk capacity in the image. Otherwise, the ECS creation may fail.

Parameter	Туре	Description
status	String	Specifies the image status. The value can be one of the following:
		• queued: indicates that the image metadata has already been created, and it is ready for the image file to upload.
		saving: indicates that the image file is being uploaded to the backend storage.
		<ul> <li>deleted: indicates that the image has been deleted.</li> <li>killed: indicates that an error occurs on the image uploading.</li> </ul>
		active: indicates that the image is available for use.
created_at	String	Specifies the time when the image was created. The value is in UTC format.
updated_at	String	Specifies the time when the image was updated. The value is in UTC format.
self	String	Specifies the image URL.
id	String	Specifies the image ID. After the image creation API is called, the image ID must be saved. The image ID is used to invoke the image uploading API and upload the image.
file	String	Specifies the URL for uploading and downloading the image file.
schema	String	Specifies the URL for accessing the schema.
image_source_type	String	Specifies the image backend storage type. Only UDS is supported currently.
image_size	String	Specifies the image size. The unit is byte.

Parameter	Туре	Description
isregistered	String	Specifies whether the image is registered. Only registered images can be queried on the portal. The value is <b>true</b> .
os_version	String	Specifies the image OS version. For the value range, see Values of Related Parameters.
os_type	String	Specifies the image OS type. The value of this parameter depends on that ofos_version. The value can be Windows, Linux, or other.
platform	String	Specifies the OS platform supported by the image. The value of this parameter depends on that ofos_version.
os_bit	String	Specifies the OS bit. The value of this parameter depends on that ofos_version. The value can be 32 or 64.
imagetype	String	Specifies the image type.  private indicates a private image.
virtual_env_type	String	Specifies the platform type.  Specifies the environment where the image is used. The value can be  FusionCompute, Ironic,  DataImage, or IsoImage.  For an ECS image, the
		<ul> <li>For an ECS image, the value is FusionCompute.</li> <li>For a data disk image, the value is DataImage.</li> <li>For a BMS image, the value is Ironic.</li> <li>For an ISO image, the value is IsoImage.</li> </ul>
owner	String	Specifies the ID of the project to which the image belongs.

Parameter	Туре	Description
root_origin	String	Specifies that the image is created from an external image file. Value: <b>file</b>
checksum	String	Specifies the MD5 value of the image file.
size	Long	This parameter is unavailable currently.
virtual_size	Integer	Specifies the virtual size of the image. The unit is byte.
properties	Properties object	Specifies a collection of image attributes instead of a specified attribute.

#### • Example response

```
STATUS CODE 201
   "schema": "/v2/schemas/image",
"min_disk": 1,
"created_at": "2016-06-02T07:49:48Z",
   "_image_source_type": "uds",
"container_format": "bare",
"_image_size": "0",
   "file": "/v2/images/4ca46bf1-5c61-48ff-b4f3-0ad4e5e3ba86/file",
   "updated_at": "2016-06-02T07:49:49Z",
   "protected": false,
   "id": "4ca46bf1-5c61-48ff-b4f3-0ad4e5e3ba86",
   "__isregistered": "true",
   "min_ram": 1024,
   "owner": "b912fb4a4c464b568ecfca1071b21b10",
   "_os_type": "Linux",

"_imagetype": "private",

"visibility": "private",

"virtual_env_type": "FusionCompute",
    "tags": [
       "test",
       "image"
   "__platform": "Ubuntu",
"__os_bit": "64",
"__os_version": "Ubuntu 14.04 server 64bit",
   "name": "test",
"self": "/v2/images/4ca46bf1-5c61-48ff-b4f3-0ad4e5e3ba86",
   "disk_format": "vhd",
   "status": "queued"
```

#### **Returned Values**

Normal201

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.1.7 Deleting an Image (Native OpenStack API v1.1 - Abandoned and Not Recommended)

#### **Function**

This API is used to delete an image. If you soft delete the image with a specified ID, the image persists in the database, but in the **deleted** status.

This API has been discarded. **Deleting an Image (Native OpenStack API)** is recommended.

#### URI

DELETE /v1.1/images/{image\_id}

Table 6-11 lists the parameters in the URI.

Table 6-11 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.

#### Request

Request parameters

None

• Example request DELETE https://{Endpoint}/v1.1/images/3c3d1d01-b48a-4639-8a88-08be3b9b5d78

#### Response

Response parameters

None

• Example response HTTP/1.1 200 OK

Content-Type: text/html; charset=UTF-8 Content-Length: 0 X-Openstack-Request-Id: req-75e9edca-7b43-47da-bdc5-d39be469b72f Date: Mon, 23 May 2016 02:43:34 GMT

#### **Returned Values**

Normal204

Abnormal

Returned Values	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.1.8 Querying Image Metadata (Native OpenStack API v1 - Abandoned and Not Recommended)

#### **Function**

This API is used to query image metadata.

This API has been discarded. The API for querying image details (Querying Image Details (Native OpenStack API)) is recommended.

#### URI

HEAD /v1/images/{image\_id}

Table 6-12 lists the parameters in the URI.

Table 6-12 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.

#### Request

Request parameters
 None

• Example request HEAD https://{Endpoint}/v1/images/3c3d1d01-b48a-4639-8a88-08be3b9b5d78

# Response

#### • Response parameters

Parameter	Туре	Description
Status	String	Image status
Virtual_size	Integer	Virtual size of an image
Name	String	Image name
Deleted	Boolean	Whether an image has been deleted
Container_format	String	Image container type
Created_at	String	Time when an image was created
Disk_format	String	Image file type
Updated_at	String	Time when an image was updated
Property	Object	Image attribute
Owner	String	Tenant to which an image belongs
Protected	Boolean	Whether an image is protected
Min_ram	Integer	Minimum memory (MB) required for running an image
Checksum	String	Image verification sum. This parameter is available after an image file is uploaded.
Min_disk	Integer	Minimum disk capacity (GB) required for running the image
Is_public	Boolean	Whether an image is a public one
Deleted_at	String	Time when an image was deleted
Id	String	Image UUID

Parameter	Туре	Description
Size	Integer	Image size. This parameter is available after an image file is uploaded.

These parameters are contained in the header of the HTTP response message.

• Example response

HTTP/1.1 200 OK

Content-Type: text/html; charset=UTF-8

Content-Length: 0

X-Image-Meta-Id: 3c3d1d01-b48a-4639-8a88-08be3b9b5d78

X-Image-Meta-Deleted: False

X-Image-Meta-Container\_format: bare

X-Image-Meta-Checksum: 64d7c1cd2b6f60c92c14662941cb7913

X-Image-Meta-Protected: False X-Image-Meta-Min\_disk: 0

X-Image-Meta-Created\_at: 2016-05-22T06:04:20.425843

X-Image-Meta-Size: 13167616 X-Image-Meta-Status: active X-Image-Meta-Is\_public: True X-Image-Meta-Min\_ram: 0

X-Image-Meta-Owner: 23f4cb75768d4febb39542ef6fe169f3 X-Image-Meta-Updated\_at: 2016-05-22T06:04:22.719791

X-Image-Meta-Disk\_format: qcow2

X-Image-Meta-Name: cirros

Etag: 64d7c1cd2b6f60c92c14662941cb7913

X-Openstack-Request-Id: req-7123ca83-da23-4f4e-9ed6-accd3707d333

Date: Mon, 23 May 2016 02:29:54 GMT

#### **Returned Values**

Normal

200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.1.9 Querying Image Details (Native OpenStack API v1.1 - Abandoned and Not Recommended)

#### **Function**

This API is used to query details of images.

This API has been discarded. The image query API (Querying Images (Native OpenStack API)) is recommended.

#### URI

GET /v1.1/images/detail

#### Request

Request parameters

Parameters name, container\_format, disk\_format, status, size\_min, size\_max, and changes-since can be used to filter the query result.

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the image name. For detailed description, see Image Attributes.
container_for mat	No	String	lmage container type
disk_format	No	String	Image file format
status	No	String	Image status
size_min	No	String	Minimum size of the image
size_max	No	String	Maximum size of the image
changes-since	No	String	Last update time

• Example request GET https://{Endpoint}/v1.1/images/detail?disk\_format=qcow2

#### Response

Response parameters

Parameter	Туре	Description
status	String	Image status
virtual_size	Integer	Virtual size of an image

Parameter	Туре	Description
name	String	Specifies the image name. For detailed description, see Image Attributes.
deleted	Boolean	Whether an image has been deleted
container_format	String	Image container type
created_at	String	Time when an image was created
disk_format	String	Image file type
updated_at	String	Time when an image was updated
properties	Object	lmage attribute
owner	String	Tenant to which an image belongs
protected	Boolean	Whether an image is protected
min_ram	Integer	Minimum memory (MB) required for running an image
checksum	String	Image verification sum. This parameter is available after an image file is uploaded.
min_disk	Integer	Minimum disk capacity (GB) required for running the image
is_public	Boolean	Whether an image is a public one
deleted_at	String	Time when an image was deleted
id	String	Image UUID
size	Integer	Image size. This parameter is available after an image file is uploaded.

# • Example response HTTP/1.1 200 OK

```
Content-Type: application/json; charset=UTF-8
Content-Length: 495
X-Openstack-Request-Id: req-68327dda-8078-41fe-b091-01a09ec073da
Date: Mon, 23 May 2016 02:32:28 GMT
  "images": [
     {
        "status": "active",
        "deleted_at": null,
        "name": "cirros",
        "deleted": false,
        "container_format": "bare",
        "created_at": "2016-05-22T06:04:20.425843",
        "disk_format": "qcow2",
        "updated_at": "2016-05-22T06:04:22.719791",
       "min_disk": 0,
        "protected": false,
        "id": "3c3d1d01-b48a-4639-8a88-08be3b9b5d78",
       "min_ram": 0,
        "checksum": "64d7c1cd2b6f60c92c14662941cb7913",
        "owner": "23f4cb75768d4febb39542ef6fe169f3",
        "is_public": true,
        "virtual_size": null,
        "properties": {
       },
"size": 13167616
  ]
```

#### **Returned Values**

- Normal200
- Abnormal

Returned Values	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.2 Image Schema (Native OpenStack APIs)

# 6.2.1 Querying an Image Schema (Native OpenStack API)

#### **Function**

This API is used to query the image schema, which allows you to view image attributes and their data types.

#### **URI**

GET /v2/schemas/image

## Request

• Request parameters

None

• Example request GET https://{Endpoint}/v2/schemas/image

## Response

#### Response parameters

Parameter	Туре	Description
additionalProperties	Object	Specifies the additional attributes. For details, see <b>Table 6-13</b> .
name	String	Specifies the schema name.
links	Array of objects	Specifies the URL for accessing the schema. For details, see <b>Table 6-14</b> .
properties	Object	Describes basic image attributes, including the type and usage of each attribute.
		For details about the parameters, see Image Attributes.

Table 6-13 Data structure description of the additional Properties field

Parameter	Туре	Description
type	String	Туре

Table 6-14 Data structure description of the links field

Parameter	Туре	Description
href	String	Specifies the domain name.
rel	String	Specifies the domain name description.

• Example response STATUS CODE 200 {

2023-02-13

"additionalProperties": {

```
"type": "string"
   "name": "image",
   "links": [
     {
        "href": "{self}",
         "rel": "self"
     },
        "href": "{file}",
        "rel": "enclosure"
         "href": "{schema}",
         "rel": "describedby"
     }
   "properties": {
      "status": {
         "enum": [
           "queued",
           "saving",
           "active",
           "killed",
           "deleted",
           "pending_delete"
        ],
"type": "string",
         "description": "Status of the image (READ-ONLY)"
     },
"tags": {
         "items": {
           "type": "string",
           "maxLength": 255
        },
"type": "array",
"description": "List of strings related to the image"
     },
"kernel_id": {
         "pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F])
{12}$",
         "type": "string",
         "description": "ID of image stored in Glance that should be used as the kernel when booting
an AMI-style image.",
         "is_base": false
     },
"container_format": {
         "enum": [
           "ami",
           "ari",
           "aki",
           "bare",
           "ovf",
           "ova"
        "type": "string",
"description": "Format of the container"
     },
"min_ram": {
         "type": "integer",
         "description": "Amount of ram (in MB) required to boot image."
      "ramdisk_id": {
         "pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F])
{12}$",
        "type": "string",
         "description": "ID of image stored in Glance that should be used as the ramdisk when booting
an AMI-style image.",
        "is_base": false
```

```
},
"locations": {
         "items": {
            "required": [
               "url",
               "metadata"
            "type": "object",
            "properties": {
               "url": {
                  "type": "string",
                  "maxLength": 255
               "metadata": {
                  "type": "object"
            }
         },
         "type": "array",
         "description": "A set of URLs to access the image file kept in external store"
     },
"visibility": {
    "enum": [
    "sublic"
            "public",
            "private"
         "type": "string",
         "description": "Scope of image accessibility"
      "updated_at": {
         "type": "string",
         "description": "Date and time of the last image modification (READ-ONLY)"
      "owner": {
         "type": "string",
"description": "Owner of the image",
"maxLength": 255
     },
"file": {
         "type": "string",
"description": "(READ-ONLY)"
      "min_disk": {
         "type": "integer",
         "description": "Amount of disk space (in GB) required to boot image."
     },
"virtual_size": {
    "" "inter
         "type": "integer",
         "description": "Virtual size of image in bytes (READ-ONLY)"
      "id": {
         "pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F])
{12}$",
         "type": "string",
         "description": "An identifier for the image"
     },
"size": {
         "type": "integer",
         "description": "Size of image file in bytes (READ-ONLY)"
     },
"instance_uuid": {
"" "string"
         "type": "string",
         "description": "ID of instance used to create this image.",
         "is_base": false
      "os_distro": {
"type": "string",
         "description": "Common name of operating system distribution as specified in http://
docs.openstack.org/trunk/openstack-compute/admin/content/adding-images.html",
```

```
"is_base": false
      "name": {
         "type": "string",
"description": "Descriptive name for the image",
"maxLength": 255
      },
"checksum": {
         "type": "string",
         "description": "md5 hash of image contents. (READ-ONLY)",
         "maxLength": 32
      },
"created_at": {
    "" "strir
         "type": "string",
         "description": "Date and time of image registration (READ-ONLY)"
      "disk_format": {
         "enum": [
"ami",
             "ari",
             "aki",
             "vhd"
             "vmdk",
             "raw",
             "qcow2",
             "vdi",
             "iso"
         "type": "string",
         "description": "Format of the disk"
       "os_version": {
         "type": "string",
         "description": "Operating system version as specified by the distributor",
         "is_base": false
      "protected": {
         "type": "boolean",
         "description": "If true, image will not be deletable."
      },
"architecture": {
         "type": "string",
"description": "Operating system architecture as specified in http://docs.openstack.org/trunk/openstack-compute/admin/content/adding-images.html",
         "is_base": false
     },
"direct_url": {
         "type": "string",
         "description": "URL to access the image file kept in external store (READ-ONLY)"
      "self": {
         "type": "string",
         "description": "(READ-ONLY)"
      "schema": {
    "type": "string",
    "description": "(READ-ONLY)"
      }
  }
```

#### **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.2.2 Querying an Image List Schema (Native OpenStack API)

#### **Function**

This API is used to query an image list schema, which allows you to know details about and the data structure of the image list.

#### **URI**

GET /v2/schemas/images

#### Request

- Request parameters
  - None
- Example request
   GET https://{Endpoint}/v2/schemas/images

#### Response

• Response parameters

Parameter	Туре	Description
name	String	Specifies the schema name.
links	Array of objects	Specifies the URL for accessing the schema.  For details, see <b>Table 6-15</b> .
properties	Object	Describes basic image attributes, including the type and usage of each attribute.  For details about the parameters, see Image Attributes.

Table 6-15 Data structure description of the links field

Parameter	Туре	Description
href	String	Specifies the domain name.
rel	String	Specifies the domain name description.

#### • Example response

```
STATUS CODE 200
   "name": "images",
   "links": [
          "href": "{first}",
"rel": "first"
           "href": "{next}",
           "rel": "next"
       },
          "href": "{schema}",
"rel": "describedby"
   ],
    "properties": {
       "images": {
    "items": {
              "additionalProperties": {
                  "type": "String"
              },
"name": "image",
"links": [
                 {
                     "href": "{self}",
"rel": "self"
                     "href": "{file}",
"rel": "enclosure"
                 },
                     "href": "{schema}",
                     "rel": "describedby"
              ],
"properties": {
                  "status": {
                     "enum": [
                         "queued",
                         "saving",
                         "active",
                         "killed",
                         "deleted",
                         "pending_delete"
                     "type": "string",
"description": "Status of the image (READ-ONLY)"
                },
"tags": {
    "items": {
    "+vpe":
                         "type": "string",
                         "maxLength": 255
```

```
"type": "array",
                 "description": "List of strings related to the image"
               "kernel_id": {
    "pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-
([0-9a-fA-F]){12}$",
                 "type": "string",
"description": "ID of image stored in Glance that should be used as the kernel when
booting an AMI-style image.",
                 "is_base": false
               "container_format": {
                  "enum": [
                     "ami",
                    "ari",
"aki",
                    "bare",
                     "ovf",
                     "ova"
                 ],
"type": "string",
"intion": "I
                 "description": "Format of the container"
               "min_ram": {
                 "type": "integer",
"description": "Amount of ram (in MB) required to boot image."
              },
"ramdisk_id": {
                 "pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-
([0-9a-fA-F]){12}$",
                  "type": "string",
                 "description": "ID of image stored in Glance that should be used as the ramdisk when
booting an AMI-style image."
                 "is_base": false
              },
"locations": {
                  "items": {
                     "required": [
                        "url",
                        "metadata"
                    ],
"type": "object",
                     "properties": {
                        "url": {
                           "type": "string",
                           "maxLength": 255
                        "metadata": {
                           "type": "object"
                    }
                 "type": "array",
"description": "A set of URLs to access the image file kept in external store"
               "visibility": {
"enum": [
                    "public"
                     "private"
                 ],
"type": "string",
"description": "Scope of image accessibility"
               "updated_at": {
                  "type": "string",
                  "description": "Date and time of the last image modification (READ-ONLY)"
               "owner": {
                  "type": "string",
```

```
"description": "Owner of the image", "maxLength": 255
               "file": {
                  "type": "string",
                 "description": "(READ-ONLY)"
               "min_disk": {
                 "type": "integer",
"description": "Amount of disk space (in GB) required to boot image."
               "virtual_size": {
                 "type": "integer",
                 "description": "Virtual size of image in bytes (READ-ONLY)"
              },
"id": {
                 "pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-
([0-9a-fA-F]){12}$",
                  "type": "string",
                 "description": "An identifier for the image"
               "size": {
                 "type": "integer",
                 "description": "Size of image file in bytes (READ-ONLY)"
               "instance_uuid": {
                 "type": "string",
                 "description": "ID of instance used to create this image.",
                  "is_base": false
               "os_distro": {
                 "type": "string",
"description": "Common name of operating system distribution as specified in http://
docs.openstack.org/trunk/openstack-compute/admin/content/adding-images.html",
                  "is_base": false
               "name": {
                 "type": "string",
"description": "Descriptive name for the image",
"maxLength": 255
              },
"checksum": {
                 "type": "string",
"description": "md5 hash of image contents. (READ-ONLY)",
                 "maxLength": 32
              },
"created_at": {
                 "type": "string",
                 "description": "Date and time of image registration (READ-ONLY)"
               "disk_format": {
                  "enum": [
                    "ami",
                    "ari",
                    "aki",
                     "vhd"
                     "vmdk",
                    "raw",
                     "qcow2",
                     "vdi",
                     "iso"
                 "type": "string",
"description": "Format of the disk"
               os_version": {
                  "type": "string",
                 "description": "Operating system version as specified by the distributor",
                 "is_base": false
```

```
"protected": {
    "type": "boolean",
                     "description": "If true, image will not be deletable."
                  "architecture": {
"type": "string",
    "description": "Operating system architecture as specified in http://docs.openstack.org/
trunk/openstack-compute/admin/content/adding-images.html",
                     "is_base": false
                 "type": "string",
                     "description": "URL to access the image file kept in external store (READ-ONLY)"
                 },
"self": {
                     "type": "string",
"description": "(READ-ONLY)"
                  "schema": {

"type": "string",

"description": "(READ-ONLY)"
              }
          },
"type": "array"
      },
"schema": {
    "type": "string"
       },
"next": {
           "type": "string"
       "first": {
           "type": "string"
   }
```

#### **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.2.3 Querying an Image Member Schema (Native OpenStack API)

#### **Function**

This API is used to query an image member schema, which allows you to view image member attributes and their data types.

#### URI

GET /v2/schemas/member

#### Request

Request parameters

None

 Example request GET https://{Endpoint}/v2/schemas/member

#### Response

Response parameters

Parameter	Туре	Description
name	String	Specifies the schema name.
properties	Object	Describes basic image attributes, including the type and usage of each attribute.
		For details about the parameters, see Image Attributes.

Example response

```
STATUS CODE 200
  "name": "member",
  "properties": {
     "status": {
        "enum": [
           "pending",
           "accepted",
           "rejected"
        "description": "The status of this image member"
     },
"created_at": {
    ". "strir
        "type": "string",
        "description": "Date and time of image member creation"
     "updated_at": {
        "type": "string",
        "description": "Date and time of last modification of image member"
     },
"image_id": {
        "pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F])
```

```
{12}$",
     "type": "string",
     "description": "An identifier for the image"
},
    "member_id": {
        "type": "string",
        "description": "An identifier for the image member (tenantId)"
},
     "schema": {
        "readOnly": true,
        "type": "string"
}
}
```

#### **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.2.4 Querying an Image Member List Schema (Native OpenStack API)

#### **Function**

This API is used to query an image member list schema, which allows you to view image member attributes and their data types.

#### **URI**

GET /v2/schemas/members

#### Request

Request parameters

None

Example request
 GET https://{Endpoint}/v2/schemas/members

#### Response

#### Response parameters

Parameter	Туре	Description
name	String	Specifies the schema name.
links	Array of objects	Specifies the URL for accessing the schema. For details, see <b>Table 6-16</b> .
properties	Object	Describes basic image attributes, including the type and usage of each attribute.
		For details about the parameters, see Image Attributes.

Table 6-16 Data structure description of the links field

Parameter	Туре	Description
href	String	Specifies the domain name.
rel	String	Specifies the domain name description.

#### • Example response

```
STATUS CODE 200
   "name": "members",
   "links": [
         "href": "{schema}",
"rel": "describedby"
      }
   "properties": {
      "members": {
    "items": {
            "name": "member",
             "properties": {
                "status": {
                   "enum": [
                      "pending",
                      "accepted",
                      "rejected"
                   "type": "string",
"description": "The status of this image member"
                "created_at": {
                   "type": "string",
"description": "Date and time of image member creation"
               },
"updated_at": {
                   "type": "string",
"description": "Date and time of last modification of image member"
                "image_id": {
```

```
"pattern": "^([0-9a-fA-F]){8}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-F]){4}-([0-9a-fA-
```

#### **Returned Values**

- Normal200
- Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.3 Image Sharing (Native OpenStack APIs)

## 6.3.1 Adding an Image Member (Native OpenStack API)

#### **Function**

This API is used to add a project ID of a tenant with whom the image is to be shared.

#### URI

POST /v2/images/{image\_id}/members

#### Request

#### Request parameters

Parame ter	Mandatory	Туре	Description
membe r	Yes	String	Specifies the image member.  The value is the project ID of a tenant.

#### • Example request

```
POST https://{Endpoint}/v2/images/d164b5df-1bc3-4c3f-893e-3e471fd16e64/members {
    "member":"edc89b490d7d4392898e19b2deb34797"
}
```

#### Response

#### • Response parameters

Parameter	Туре	Description
status	String	Specifies the image sharing status.
created_at	String	Specifies the time when a shared image was created. The value is in UTC format.
updated_at	String	Specifies the time when a shared image was updated. The value is in UTC format.
image_id	String	Specifies the image ID.
member_id	String	Specifies the member ID, that is, the project ID of the tenant who is to accept the shared image.
schema	String	Specifies the sharing schema.

#### Example response

```
STATUS CODE 200
{
    "status": "pending",
    "created_at": "2016-09-01T02:05:14Z",
    "updated_at": "2016-09-01T02:05:14Z",
    "image_id": "d164b5df-1bc3-4c3f-893e-3e471fd16e64",
    "member_id": "edc89b490d7d4392898e19b2deb34797",
    "schema": "/v2/schemas/member"
}
```

#### **Returned Values**

Normal

200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.3.2 Updating the Image Sharing Status in Batches (Native OpenStack API)

#### **Function**

This API is used to update the image sharing status when a tenant accepts or rejects a shared image.

#### URI

PUT /v2/images/{image\_id}/members/{member\_id}

Table 6-17 lists the parameters in the URI.

Table 6-17 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.
member_id	Yes	String	Specifies the member ID.

#### Request

• Request parameters

Parameter	Mandatory	Туре	Description
status	Yes	String	Specifies whether a shared image will be accepted or declined.
			Available values include:
			accepted: indicates that a shared image is accepted. After an image is accepted, the image is displayed in the image list. You can use the image to create ECSs.
			rejected: indicates that a shared image is declined.     After an image is rejected, the image is not displayed in the image list. However, you can still use the image to create ECSs.
vault_id	Yes	String	Specifies the vault ID.
			You can obtain the vault ID from the CBR console or section "Querying the Vault List" in <i>Cloud Backup and Recovery API Reference</i> .

#### Example request

If the image is not a full-ECS image: PUT https://{Endpoint}/v2/images/d164b5df-1bc3-4c3f-893e-3e471fd16e64/ members/edc89b490d7d4392898e19b2deb34797 { "status": "accepted" }

- If the image is a full-ECS image:

```
PUT https://{Endpoint}/v2/images/d164b5df-1bc3-4c3f-893e-3e471fd16e64/members/edc89b490d7d4392898e19b2deb34797
{
    "status": "accepted",
    "vault_id": "6yhtb5df-1bc3-4c3f-893e-3e4716yhgt61"
}
```

#### Response

#### • Response parameters

Parameter	Туре	Description	
status	String	Specifies the image sharing status.	
created_at	String	Specifies the time when a shared image was created. The value is in UTC format.	

Parameter	Туре	Description	
updated_at	String	Specifies the time when a shared image was updated. The value is in UTC format.	
image_id	String	Specifies the image ID.	
member_id	String	Specifies the member ID.	
schema	String	Specifies the sharing schema.	

• Example response

```
STATUS CODE 200

{
    "status": "accepted",
    "created_at": "2016-09-01T02:05:14Z",
    "updated_at": "2016-09-01T02:37:11Z",
    "image_id": "d164b5df-1bc3-4c3f-893e-3e471fd16e64",
    "member_id": "edc89b490d7d4392898e19b2deb34797",
    "schema": "/v2/schemas/member"
}
```

#### **Returned Values**

Normal

200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.3.3 Querying Image Member Details (Native OpenStack API)

#### **Function**

This API is used to query details about a tenant with whom the image is shared.

#### **URI**

GET /v2/images/{image\_id}/members/{member\_id}

Table 6-18 lists the parameters in the URI.

**Table 6-18** Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.
member_id	Yes	String	Specifies the member ID.

#### Request

Request parameters

None

• Example request

GET https://{Endpoint}/v2/images/d164b5df-1bc3-4c3f-893e-3e471fd16e64/members/edc89b490d7d4392898e19b2deb34797

#### Response

• Response parameters

Parameter	Туре	Description
status	String	Specifies the image sharing status.
created_at	String	Specifies the time when a shared image was created. The value is in UTC format.
updated_at	String	Specifies the time when a shared image was updated. The value is in UTC format.
image_id	String	Specifies the image ID.
member_id	String	Specifies the member ID.
schema	String	Specifies the sharing schema.

• Example response

```
STATUS CODE 200
{
    "status": "accepted",
    "created_at": "2016-09-01T02:05:14Z",
    "updated_at": "2016-09-01T02:37:11Z",
    "image_id": "d164b5df-1bc3-4c3f-893e-3e471fd16e64",
    "member_id": "edc89b490d7d4392898e19b2deb34797",
    "schema": "/v2/schemas/member"
}
```

#### **Returned Values**

Normal200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.3.4 Querying Image Members (Native OpenStack API)

#### **Function**

This API is used to query the tenants with whom an image is shared using search criteria and to display the tenants in a list.

#### URI

GET /v2/images/{image\_id}/members

Table 6-19 lists the parameters in the URI.

Table 6-19 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.

#### Request

• Request parameters

None

• Example request

GET https://{Endpoint}/v2/images/d164b5df-1bc3-4c3f-893e-3e471fd16e64/members

#### Response

• Response parameters

Parameter	Type Description	
members	Array of objects	Specifies the members. For details, see <b>Table 6-20</b> .
schema	String	Specifies the sharing schema.

<b>Table 6-20</b> L	ata structure	description of	the members fie	ld

Parameter	Туре	Description
status	String	Specifies the image sharing status.
created_at	String	Specifies the time when a shared image was created. The value is in UTC format.
updated_at	String	Specifies the time when a shared image was updated. The value is in UTC format.
image_id	String	Specifies the image ID.
member_id	String	Specifies the member ID.
schema	String	Specifies the sharing schema.

• Example response

#### **Returned Values**

Normal

200

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

## 6.3.5 Deleting an Image Member (Native OpenStack API)

#### **Function**

This API is used to stop image sharing by deleting the tenant with whom the image is shared.

#### URI

DELETE /v2/images/{image\_id}/members/{member\_id}

Table 6-21 lists the parameters in the URI.

Table 6-21 Parameter description

Parameter	Mandatory	Туре	Description
image_id	Yes	String	Specifies the image ID.
member_id	Yes	String	Specifies the member ID.

#### Request

Request parameters

None

• Example request DELETE https://{Endpoint}/v2/images/d164b5df-1bc3-4c3f-893e-3e471fd16e64/members/edc89b490d7d4392898e19b2deb34797

#### Response

• Response parameters

None

• Example response 204 No Content

#### **Returned Values**

Normal204

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.

Returned Value	Description
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# 6.4 API Version Query (Native OpenStack API)

# 6.4.1 Querying API Versions (Native OpenStack API)

#### **Function**

This API is used to query API versions, such as version compatibility and domain name information of APIs.

#### **URI**

GET /

#### Request

- Request parameters None
- Example request GET https://{Endpoint}/

#### Response

• Response parameters

Parameter	Туре	Description
versions	Array of objects	Specifies the versions. For details, see <b>Table</b>
		6-22.

Table 6-22 Data structure description of the versions field

Parameter	Туре	Description
status	String	Specifies the API status.
id	String	Specifies the API ID.
links	Array of objects	Specifies the description.
		For details, see <b>Table 6-23</b> .

Table 6-23 Data structure description of the versions.links field

Parameter	Туре	Description
href	String	Specifies the domain name.
rel	String	Specifies the domain name description.

#### • Example response

```
STATUS CODE 300
  "versions": [
        "status": "CURRENT",
        "id": "v2.2",
        "links": [
             "href": "https://image.az1.dc1.domainname.com/v2/",
             "rel": "self"
       ]
     },
{
        "status": "SUPPORTED",
        "id": "v2.1",
        "links": [
             "href": "https://image.az1.dc1.domainname.com/v2/",
             "rel": "self"
       ]
     },
        "status": "SUPPORTED",
        "id": "v2.0",
        "links": [
          {
             "href": "https://image.az1.dc1.domainname.com/v2/",
             "rel": "self"
          }
        ]
     },
        "status": "DEPRECATED",
        "id": "v1.1",
        "links": [
             "href": "https://image.az1.dc1.domainname.com/v1/",
             "rel": "self"
           }
        ]
     },
        "status": "DEPRECATED",
        "id": "v1.0",
        "links": [
             "href": "https://image.az1.dc1.domainname.com/v1/",
             "rel": "self"
           }
        ]
```

] ] }

#### **Returned Values**

Normal300

Abnormal

Returned Value	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

## 6.4.2 Querying an API Version (Native OpenStack API)

#### **Function**

This API is used to query a specified API version, such as version compatibility and domain name information of an API.

#### URI

GET /{api\_version}

Table 6-24 lists the parameters in the URI.

Table 6-24 Parameter description

Parameter	Mandatory	Туре	Description
api_version	Yes	String	Specifies the API version, for example v2.0.

#### Request

Request parameters

None

 Example request GET https://{Endpoint}/v2.0

#### Response

#### Response parameters

Parameter	Туре	Description
versions	Array of objects	Specifies the version. For details, see <b>Table 6-25</b> .

Table 6-25 Data structure description of the versions field

Parameter	Туре	Description
status	String	Specifies the API status.
id	String	Specifies the API ID.
links	Array of objects	Specifies the description.
		For details, see <b>Table 6-26</b> .

Table 6-26 Data structure description of the versions.links field

Parameter	Туре	Description
href	String	Specifies the domain name.
rel	String	Specifies the domain name description.

#### • Example response

#### **Returned Values**

Normal300

#### • Abnormal

Returned Values	Description
400 Bad Request	Request error.
401 Unauthorized	Authentication failed.
403 Forbidden	You do not have the rights to perform the operation.
404 Not Found	The requested resource was not found.
500 Internal Server Error	Internal service error.
503 Service Unavailable	The service is unavailable.

# **7** Examples

## 7.1 Creating an Image from an ISO File

#### **Scenarios**

An ISO file is a disk image of an optical disc. A large number of data files can be compressed into a single ISO file. Likewise, to access the files stored in an ISO, the ISO file needs to be decompressed. For example, you can use a virtual CD-ROM to open an ISO file, or burn the ISO file to a CD or DVD and then use the CD-ROM to read the image.

This section describes how to use APIs to create a private image from an ISO file.

#### **Involved APIs**

If you use a token for authentication, you must obtain the token and add **X-Auth-Token** to the request header of the IMS API when making an API call.

- IAM API used to obtain the token
  - URI format: POST https://IAM endpoint/v3/auth/tokens
- IMS API used to create a private image using an image file uploaded to the OBS bucket
  - URI format: POST https://IMS endpoint/v2/cloudimages/action
- ECS API used to create an ECS
  - URI format: POST https://ECS endpoint/v1/project id/cloudservers
- IMS API used to create a system disk image from a data disk
   URI format: POST https://IMS endpoint/v2/cloudimages/action

#### **Procedure**

- 1. Obtain the token by referring to **Authentication**.
- 2. Create a private image using an ISO image file uploaded to the OBS bucket.
  - a. Send **POST https://***IMS endpoint*/**v2/cloudimages/action**.

- b. Add X-Auth-Token to the request header.
- c. Set the following parameters in the request body:

For details about the parameters, see Creating an Image.

```
{
    "name": "ims_test_file", //Image name (mandatory, string)
    "description": "Image creation using an image file uploaded to the OBS bucket", //Image
description (optional, string)
    "image_url": "ims-image:centos70.iso", //Image file address (mandatory, string)
    "os_type": "Linux", //OS type (optional, string)
    "os_version": "CentOS 7.0 64bit", //OS version (mandatory, string)
    "type": "IsoImage", //Image type (mandatory, string)
    "min_disk": 40, //Minimum system disk space (mandatory, integer)
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}] //Image tags
(optional, array of objects)
}
```

- d. Obtain the image ID by querying job details based on the returned **job\_id**. For details, see **Asynchronous Job Query**.
- 3. Create a temporary ECS from the ISO image.

#### 

- You can select only a general-computing flavor with 2 vCPUs, 4 GB or more memory, and KVM virtualization type.
- You need to create a system disk and a data disk for the ECS. The OS will be installed on the data disk by default.
- a. Send **POST https://***ECS endpoint*/**v1**/*project\_id*/**cloudservers**.
- b. Add X-Auth-Token to the request header.
- c. Set the following parameters in the request body:

The following parameters are all mandatory. For details about the parameters, see "Creating an ECS" in *Elastic Cloud Server API Reference*.

```
"server": {
   "imageRef": "fac42d61-ea1e-4271-94ba-6543a852d2c6", //Image ID "flavorRef": "rc6.large.2_manage",
   "name": "instance-test",
   "vpcid": "18ec99f0-7159-4d7b-ad27-f32315d5af61",
   "nics": [{
      "subnet_id": "81a4ecb0-0451-4c60-8373-8b923238ec40"
   "root_volume": {
      "volumetype": "SATA",
      "size": "40"
   "data_volumes": [{
      "volumetype": "SATA",
      "size": "40"
   "availability_zone": "az-1a",
   "metadata": {
      "virtual_env_type": "IsoImage"
   "extendparam": {
      "diskPrior": "true"
}
```

d. Obtain the ECS ID by querying job details based on the returned **job\_id**. For details, see "Querying Task Execution Status" in *Elastic Cloud Server API Reference*.

- e. Query ECS details based on the ECS ID to obtain the data disk ID (**volume\_id**) required in **4**. For details, see "Querying Details About an ECS" in *Elastic Cloud Server API Reference*.
- 4. Use the temporary ECS to create a standard private image.
  - a. Send **POST https://**IMS endpoint/v2/cloudimages/action.
  - b. Add X-Auth-Token to the request header.
  - Set the following parameters in the request body:
     For details about the parameters, see Creating an Image.

```
{
    "name": "ims_test", //Image name (a mandatory string)
    "description": "Creating a system disk image from a data disk", //Image description (optional, string)
    "volume_id": "877a2cda-ba63-4e1e-b95f-e67e48b6129a", //Data disk ID (mandatory, string)
    "type": "ECS", //Image type (mandatory, string)
    "os_version": "CentOS 7.0 64bit", //OS version (mandatory, string)
    "image_tags": [{"key":"key2","value":"value2"},{"key":"key1","value":"value1"}] //Image tags
(optional, array of objects)
}
```

d. Obtain the image ID by querying job details based on the returned **job\_id**. For details, see **Asynchronous Job Query**.

# 8 Permission Policies and Supported Actions

#### 8.1 Introduction

This section describes fine-grained permissions management for your IMS. If your account does not need individual IAM users, you may skip over this section.

By default, new IAM users do not have any permissions assigned. You need to add a user to one or more groups, and assign policies or roles to these groups. The user then inherits permissions from the groups it is a member of. This process is called authorization. After authorization, the user can perform specified operations on cloud services based on the permissions.

You can grant user permissions by using roles and policies.

- Roles: A type of coarse-grained authorization mechanism that defines permissions related to user responsibilities. This mechanism provides only a limited number of service-level roles for authorization.
- Policies: A type of fine-grained authorization mechanism that defines permissions required to perform operations on specific cloud resources under certain conditions. This mechanism allows for API-level policies for authorization, meeting requirements for secure access control.

#### 

Policy-based authorization is useful if you want to allow or deny the access to an API.

An account has all of the permissions required to call all APIs, but IAM users must have the required permissions specifically assigned. The permissions required for calling an API are determined by the actions supported by the API. Only users who have been granted permissions allowing the actions can call the API successfully. For example, if an IAM user queries images using an API, the user must have been granted permissions that allow the **ims:images:list** action.

#### **Supported Actions**

IMS provides system-defined policies. You can also create custom policies for more specific access control. The following are related concepts:

- Permissions: Allow or deny certain operations.
- APIs: APIs that will be called for performing certain operations.
- Actions: Operations that will be allowed or denied.
- Dependent actions: When assigning permissions for an action, you also need to assign permissions for the dependent actions.
- IAM projects or enterprise projects: Applicable scope of custom policies. For
  example, if an action supports both IAM and enterprise projects, the policy
  that contains this action will take effect for user groups assigned in IAM and
  Enterprise Management. If an action supports only IAM projects, the policy
  will take effect only for user groups assigned in IAM.

#### **◯** NOTE

√: supported; x: not supported

IMS supports the following actions that can be defined in custom policies:

- Image Management, including actions supported by IMS's image management APIs, such as the APIs for querying images, updating image information, creating images, registering images, and exporting images.
- Image Schema, including actions supported by IMS's image schema management APIs, such as the APIs for querying an image schema, querying an image list schema, querying an image member schema, and query an image member list schema.
- Image Sharing, including actions supported by IMS's shared image APIs, such as the APIs for adding an image member, updating the status of image members, querying image member details, and deleting an image member.
- Image Replication, including actions supported by IMS's image replication APIs, such as the API for replicating an image within a region.
- Image Quota, including actions supported by IMS's image quota APIs, such as the API for querying image quotas.

#### □ NOTE

Error messages returned for native OpenStack APIs are in XML format. JSON format of the fine-grained policy is not supported.

#### 8.2 Image Management

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Querying Images	GET /v2/cloudimages	ims:images:list	√	√

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Updating Image Informati on	PATCH /v2/ cloudimages/ {image_id}	<ul> <li>ims:images:up date</li> <li>ims:serverImag es:create (only for migration to enterprise projects)</li> </ul>	✓	✓
Creating an Image	POST /v2/ cloudimages/action  NOTE  Before creating an image using an external image file, ensure that you have the Tenant Administrator permission for OBS.	ims:serverlmages: create	✓	✓
Importing an Image File Quickly	POST /v2/ cloudimages/ quickimport/action  NOTE  Before quickly importing an image file, ensure that you have the Tenant Administrator permission for OBS.	<ul> <li>ims:serverImag es:create (required only for quickly importing system disk images)</li> <li>ims:dataImage s:create (required only for quickly importing data disk images)</li> </ul>	✓	✓
Creating a Data Disk Image Using an External Image File	POST /v1/ cloudimages/ dataimages/action  NOTE  Before using an external image file, ensure that you have the Tenant Administrator permission for OBS.	ims:datalmages:cr eate	√	✓

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Creating a Full-ECS Image	POST /v1/ cloudimages/ wholeimages/action  NOTE  Before creating a full- ECS image, ensure that you have the CBR Admin permission of the CBR service.	ims:wholeImages: create	✓	✓
Registerin g an Image	PUT /v1/ cloudimages/ {image_id}/upload  NOTE  Before registering an image file, ensure that you have the Tenant Administrator permission for OBS.	ims:images:uploa d	✓	<b>√</b>
Exporting an Image	POST /v1/ cloudimages/ {image_id}/file  NOTE  Before exporting an image, ensure that you have the Tenant Administrator permission for OBS.	ims:images:export	✓	~
Querying Images (Native OpenStac k API)	GET /v2/images	ims:images:list	✓	x
Querying Image Details (Native OpenStac k API)	GET /v2/images/ {image_id}	ims:images:get	√	✓
Updating Image Informati on (Native OpenStac k API)	PATCH /v2/images/ {image_id}	ims:images:updat e	√	✓

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Deleting an Image (Native OpenStac k API)	DELETE /v2/images/ {image_id}	ims:images:delete	✓	✓
Creating Image Metadata (Native OpenStac k API)	POST /v2/images	ims:images:create	✓	x
Uploadin g an Image (Native OpenStac k API)	PUT /v2/images/ {image_id}/file	<ul><li>ims:images:get</li><li>ims:images:up date</li><li>ims:images:upl oad</li></ul>	√	X
Querying the API Version (Native OpenStac k API)	GET /	N/A	√	x
Querying Image Details (Native OpenStac k API v1.1 - Abandone d and Not Recomme nded)	GET /v1.1/images/ detail	ims:images:list	<b>√</b>	x
Querying Image Metadata (Native OpenStac k API v1 - Abandone d and Not Recomme nded)	HEAD /v1/images/ {image_id}	ims:images:get	<b>√</b>	x

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Deleting an Image (Native OpenStac k API V1.1, Abandone d and Not Recomme nded)	DELETE /v1.1/ images/{image_id}	ims:images:delete	<b>√</b>	x

# 8.3 Image Schema

Permissi ons	APIs	Actions	IAM Project	Enterpris e Project
Querying an Image Schema (Native OpenStac k API)	GET /v2/schemas/ image	N/A	✓	х
Querying an Image List Schema (Native OpenStac k API)	GET /v2/schemas/ images	N/A	<b>√</b>	x
Querying an Image Member Schema (Native OpenStac k API)	GET /v2/schemas/ member	N/A	√	х

Permissi ons	APIs	Actions	IAM Project	Enterpris e Project
Querying an Image Member List Schema (Native OpenStac k API)	GET /v2/schemas/ members	N/A	√	х

# 8.4 Image Sharing

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Adding an Image Member (Native OpenStac k API)	POST /v2/images/ {image_id}/members	<ul><li>ims:images:ge t</li><li>ims:images:sh are</li></ul>	√	x
Updating the Image Sharing Status in Batches (Native OpenStac k API)	PUT /v2/images/ {image_id}/members/ {member_id}	<ul><li>ims:images:ge t</li><li>ims:images:sh are</li></ul>	✓	x
Querying Image Member Details (Native OpenStac k API)	GET /v2/images/ {image_id}/members/ {member_id}	<ul><li>ims:images:ge t</li><li>ims:images:sh are</li></ul>	√	x
Querying Image Members (Native OpenStac k API)	GET /v2/images/ {image_id}/members	<ul><li>ims:images:ge t</li><li>ims:images:sh are</li></ul>	√	x

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Deleting an Image Member (Native OpenStac k API)	DELETE /v2/images/ {image_id}/members/ {member_id}	<ul><li>ims:images:ge t</li><li>ims:images:sh are</li></ul>	√	х
Adds image members.	POST /v1/ cloudimages/ members	ims:images:share	√	Х
Updates the status of image members in batches.	PUT /v1/ cloudimages/ members	ims:images:share	√	х
Deletes image members in batches.	DELETE /v1/ cloudimages/ members	ims:images:share	✓	х

# 8.5 Image Replication

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Replicatin g an Image Within a Region	POST /v1/ cloudimages/ {image_id}/copy	<ul> <li>ims:images:co         py</li> <li>ims:serverImag         es:create         (required only         for users who         have enabled         the enterprise         project)</li> </ul>	✓	√
Replicatin g an Image Across Regions	POST /v1/ cloudimages/ {image_id}/ cross_region_copy	ims:images:copy	√	х

## 8.6 Image Quota

Permissio ns	APIs	Actions	IAM Project	Enterpris e Project
Queries the image quota	GET /v1/ cloudimages/quota	ims:quotas:get	√	√

## **9** Common Parameters

## 9.1 Image Attributes

#### Description

An image is an ECS template containing mandatory software, such as an OS. The template may also contain application software, such as database software, and proprietary software. Image is the core object of IMS.

#### **Image Attributes**

Name	Туре	Description
file	String	Specifies the URL for uploading and downloading the image file.
owner	String	Specifies the tenant to which the image belongs.
id	String	Specifies the image ID.
size	Long	This parameter is unavailable currently.
self	String	Specifies the image URL.
schema	String	Specifies the image schema.
status	String	Specifies the image status. The value can be active, queued, saving, deleted, or killed. An image can be used only when it is in the active state.
tags	Array of strings	Lists the image tags.
visibility	String	Specifies whether the image can be seen by other tenants. The value can be <b>private</b> , <b>public</b> , or <b>shared</b> .

Name	Туре	Description
name	String	Specifies the image name.
		The name cannot start or end with a space.
		• The name contains 1 to 128 characters.
		The name contains the following characters:
		- Uppercase letters
		<ul> <li>Lowercase letters</li> </ul>
		- Digits
		<ul> <li>Special characters, including hyphens         (-), periods (.), underscores (_), and         space</li> </ul>
checksum	String	This parameter is unavailable currently.
deleted	Boolean	Specifies whether the image has been deleted. The value can be <b>true</b> or <b>false</b> .
protected	Boolean	Specifies whether the image is protected. A protected image cannot be deleted. The value can be <b>true</b> or <b>false</b> .
container_for mat	String	Specifies the container type.
min_ram	Integer	Specifies the minimum memory size (MB) required for running the image. The parameter value depends on the ECS specifications. The default value is <b>0</b> .
update_at	String	Specifies the time when the image was updated.
os_bit	String	Specifies the OS architecture, 32 bit or 64 bit.
os_version	String	Specifies the OS version.
description	String	Provides supplementary information about the image.
		The value contains a maximum of 1024 characters and consists of only letters and digits. Carriage returns and angle brackets (< >) are not allowed.
disk_format	String	Specifies the image format. The value can be zvhd2, vhd, zvhd, raw, iso, or qcow2. The default value is zvhd2 for a non-ISO image.
isregistered	String	Specifies whether the image has been registered. The value can be <b>true</b> or <b>false</b> .

Name	Туре	Description
platform	String	Specifies the image platform type. The value can be Windows, Ubuntu, Red Hat, SUSE, CentOS, Debian, OpenSUSE, Oracle Linux, Fedora, Other, CoreOS, or EulerOS.
os_type	String	Specifies the OS type. The value can be Linux, Windows, or Other.
min_disk	Integer	Specifies the minimum disk space (GB) required for running the image.
virtual_env_ty pe	String	Specifies the environment where the image is used. The value can be <b>FusionCompute</b> , <b>Ironic</b> , <b>DataImage</b> , or <b>IsoImage</b> .
		<ul> <li>For an ECS image (system disk image), the value is FusionCompute.</li> </ul>
		For a data disk image, the value is     DataImage.
		For a BMS image, the value is Ironic.
		• For an ISO image, the value is <b>IsoImage</b> .
image_sour ce_type	String	Specifies the image backend storage type. Only UDS is supported currently.
imagetype	String	Specifies the image type. The following types are supported:
		Public image: The value is <b>gold</b> .
		Private image: The value is <b>private</b> .
		Shared image: The value is <b>shared</b> .
whole_ima ge	Boolean	Specifies whether the image is a full-ECS image. The value can be <b>true</b> or <b>false</b> .
create_at	String	Specifies the time when the image was created.
virtual_size	Integer	This parameter is unavailable currently.
deleted_at	String	Specifies the time when the image was deleted.
_originalima	String	Specifies the parent image ID.
gename		If the image is a public image or created from an image file, this value is left empty.
backup_id	String	Specifies the backup ID. To create an image using a backup, set the value to the backup ID. Otherwise, this value is left empty.
image_loca tion	String	Specifies the location where the image is stored.

Name	Туре	Description
image_size	String	Specifies the size (bytes) of the image file.
data_origin	String	Specifies the image source.  If the image is a public image, this parameter is left empty.
hw_firmware _type	String	Specifies the ECS boot mode. The following values are supported:  • bios indicates the BIOS boot mode.  • uefi indicates the UEFI boot mode.
support_kv m	String	Specifies whether the image supports KVM. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xe n	String	Specifies whether the image supports Xen. If yes, the value is <b>true</b> . Otherwise, this parameter is not required.
support_lar gememory	String	Specifies whether the image supports large- memory ECSs. If the image supports large- memory ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_dis kintensive	String	Specifies whether the image supports disk- intensive ECSs. If the image supports disk- intensive ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_hig hperformanc e	String	Specifies whether the image supports high- performance ECSs. If the image supports high-performance ECSs, the value is <b>true</b> . Otherwise, this parameter is not required.
support_xe n_gpu_type	String	Specifies whether the image supports GPU-accelerated ECSs on the Xen platform. For the supported OSs, see <b>Table 9-2</b> . If the image does not support GPU-accelerated ECSs on the Xen platform, this parameter is not required. This parameter cannot co-exist with <b>support_xen</b> and <b>support_kvm</b> .
support_kv m_gpu_type	String	Specifies whether the image supports GPU- accelerated ECSs on the KVM platform. See Table 9-3 for its value.
		If the image does not support GPU-accelerated ECSs on the KVM platform, this parameter is not required. This attribute cannot co-exist withsupport_xen andsupport_kvm.

Name	Туре	Description
is_config_in it	String	Specifies whether initial configuration is complete. The value can be <b>true</b> or <b>false</b> .
		If initial configuration is complete, the value is set to <b>true</b> . Otherwise, the value is set to <b>false</b> . The default value is <b>false</b> .

## 9.2 Image Tag Data Formats

#### Description

You can attach a custom tag to a private image to facilitate private image management.

#### **Data Formats**

#### Data format of tag

- The data format is *key.value*. If a key is added, a tag is added. In other cases, the tag is modified.
- When the tag contains multiple decimal points, the content before the first decimal point is the key, and that after the first decimal point is the value. If the content after the first decimal point still contains decimal points, the content as a whole is considered as the value. If the tag contains no decimal point, the value is regarded as an empty character string.
- The tag key can contain a maximum of 36 characters, and the tag value can contain a maximum of 43 characters. The tag value can be an empty character string.
- The tag key can only consist of digits, letters, underscores (\_), and hyphens (-).
- The tag key must be unique and cannot be empty.
- The tag value can only consist of digits, letters, underscores (\_), periods (.), and hyphens (-).

#### Data format of **image\_tags**

- The data format is {"key": "keyA", "value": "valueA"}. If the added key A exists, the tag is updated.
- The tag key can contain a maximum of 36 characters, and the tag value can contain a maximum of 43 characters. The tag value can be an empty character string.
- The tag key can only consist of digits, letters, underscores (\_), and hyphens (-).
- The tag key must be unique and cannot be empty.
- The tag value can only consist of digits, letters, underscores (\_), periods (.), and hyphens (-).

#### **Data Formats (Native OpenStack)**

Data format of tag

- The data format is *key*. If a key is added, a tag is added. In other cases, the tag is modified.
- The tag key can contain a maximum of 255 characters.
- The character string cannot contain equal signs (=).

## 9.3 Restrictions on Image Sharing

#### Description

You can use the image sharing function to share your private images with other users.

#### **Constraints**

- Images can only be shared within a region.
- A system disk image or data disk image can be shared with a maximum of 128 tenants, and a full-ECS image can be shared with a maximum of 10 tenants.
- You can stop sharing images anytime without notifying the recipient.
- You can delete shared image anytime without notifying the recipient.
- Encrypted images cannot be shared.
- Only full-ECS images created from CBR backups can be shared. Full-ECS images created using other methods cannot be shared.

## 9.4 Obtaining a Project ID

#### **Scenarios**

A project ID is required for some URLs when an API is called. Therefore, you need to obtain a project ID in advance. Two methods are available:

- Obtain the Project ID by Calling an API
- Obtain the Project ID from the Console

#### Obtain the Project ID by Calling an API

You can obtain the project ID by calling the IAM API used to query project information based on the specified criteria.

The API used to obtain a project ID is GET https://{Endpoint}/v3/projects. {Endpoint} is the IAM endpoint and can be obtained from **Regions and Endpoints**. For details about API authentication, see **Authentication**.

The following is an example response. The value of **id** is the project ID.

```
{
 "projects": [
```

```
"domain_id": "65382450e8f64ac0870cd180d14e684b",
      "is_domain": false,
      "parent_id": "65382450e8f64ac0870cd180d14e684b", 
"name": "project_name",
      "description": "",
      "links": {
         "next": null,
         "previous": null,
         "self": "https://www.example.com/v3/projects/a4a5d4098fb4474fa22cd05f897d6b99"
      },
"id": "a4a5d4098fb4474fa22cd05f897d6b99",
      "enabled": true
   }
],
"links": {
   "next": null,
   "previous": null,
   "self": "https://www.example.com/v3/projects"
}
```

#### Obtain a Project ID from the Console

To obtain a project ID from the console, perform the following operations:

- 1. Log in to the management console.
- Click the username and select My Credentials from the drop-down list.
   On the My Credentials page, view the project ID (value in the Project ID column).

## 9.5 Values of Related Parameters

### \_os\_version Values

**Table 9-1** \_os\_version values

OS Type	OS Version (_os_version)
Windows	Windows 10 64bit
	Windows Server 2019 Standard 64bit
	Windows Server 2019 Datacenter 64bit
	Windows Server 2016 Standard 64bit
	Windows Server 2016 Datacenter 64bit
	Windows Server 2012 R2 Standard 64bit
	Windows Server 2012 Essentials R2 64bit
	Windows Server 2012 R2 Datacenter 64bit
	Windows Server 2012 Datacenter 64bit
	Windows Server 2012 Standard 64bit
	Windows Server 2008 R2 WEB 64bit
	Windows Server 2008 R2 Standard 64bit
	Windows Server 2008 R2 Enterprise 64bit
	Windows Server 2008 R2 Datacenter 64bit
SUSE	SUSE Linux Enterprise Server 15 SP1 64bit
	SUSE Linux Enterprise Server 15 64bit
	SUSE Linux Enterprise Server 12 SP5 64bit
	SUSE Linux Enterprise Server 12 SP4 64bit
	SUSE Linux Enterprise Server 12 SP3 64bit
	SUSE Linux Enterprise Server 12 SP2 64bit
	SUSE Linux Enterprise Server 12 SP1 64bit
	SUSE Linux Enterprise Server 11 SP4 64bit
	SUSE Linux Enterprise Server 11 SP3 64bit
	SUSE Linux Enterprise Server 11 SP3 32bit

OS Type	OS Version (_os_version)
Oracle Linux	Oracle Linux Server release 7.6 64bit
	Oracle Linux Server release 7.5 64bit
	Oracle Linux Server release 7.4 64bit
	Oracle Linux Server release 7.3 64bit
	Oracle Linux Server release 7.2 64bit
	Oracle Linux Server release 7.1 64bit
	Oracle Linux Server release 7.0 64bit
	Oracle Linux Server release 6.10 64bit
	Oracle Linux Server release 6.9 64bit
	Oracle Linux Server release 6.8 64bit
	Oracle Linux Server release 6.7 64bit
	Oracle Linux Server release 6.5 64bit
Red Hat	Red Hat Linux Enterprise 8.0 64bit
	Red Hat Linux Enterprise 7.6 64bit
	Red Hat Linux Enterprise 7.5 64bit
	Red Hat Linux Enterprise 7.4 64bit
	Red Hat Linux Enterprise 7.3 64bit
	Red Hat Linux Enterprise 7.2 64bit
	Red Hat Linux Enterprise 7.1 64bit
	Red Hat Linux Enterprise 7.0 64bit
	Red Hat Linux Enterprise 6.10 64bit
	Red Hat Linux Enterprise 6.9 64bit
	Red Hat Linux Enterprise 6.8 64bit
	Red Hat Linux Enterprise 6.7 64bit
	Red Hat Linux Enterprise 6.6 64bit
	Red Hat Linux Enterprise 6.6 32bit
	Red Hat Linux Enterprise 6.5 64bit
	Red Hat Linux Enterprise 6.4 64bit
	Red Hat Linux Enterprise 6.4 32bit

OS Type	OS Version (_os_version)
Ubuntu	Ubuntu 19.04 server 64bit
	Ubuntu 18.04.2 server 64bit
	Ubuntu 18.04.1 server 64bit
	Ubuntu 18.04 server 64bit
	Ubuntu 16.04.6 server 64bit
	Ubuntu 16.04.5 server 64bit
	Ubuntu 16.04.4 server 64bit
	Ubuntu 16.04.3 server 64bit
	Ubuntu 16.04.2 server 64bit
	Ubuntu 16.04 server 64bit
	Ubuntu 14.04.5 server 64bit
	Ubuntu 14.04.4 server 64bit
	Ubuntu 14.04.4 server 32bit
	Ubuntu 14.04.3 server 64bit
	Ubuntu 14.04.3 server 32bit
	Ubuntu 14.04.1 server 64bit
	Ubuntu 14.04.1 server 32bit
	Ubuntu 14.04 server 64bit
	Ubuntu 14.04 server 32bit
openSUSE	openSUSE 42.3 64bit
	openSUSE 42.2 64bit
	openSUSE 42.1 64bit
	openSUSE 15.0 64bit
	openSUSE 13.2 64bit
	openSUSE 11.3 64bit

OS Type	OS Version (os_version)
CentOS	CentOS 8.0 64bit
	CentOS 7.7 64bit
	CentOS 7.6 64bit
	CentOS 7.5 64bit
	CentOS 7.4 64bit
	CentOS 7.3 64bit
	CentOS 7.2 64bit
	CentOS 7.1 64bit
	CentOS 7.0 64bit
	CentOS 7.0 32bit
	CentOS 6.10 64bit
	CentOS 6.10 32bit
	CentOS 6.9 64bit
	CentOS 6.8 64bit
	CentOS 6.7 64bit
	CentOS 6.7 32bit
	CentOS 6.6 64bit
	CentOS 6.6 32bit
	CentOS 6.5 64bit
	CentOS 6.5 32bit
	CentOS 6.4 64bit
	CentOS 6.4 32bit
	CentOS 6.3 64bit
	CentOS 6.3 32bit
Debian	Debian GNU/Linux 10.0.0 64bit
	Debian GNU/Linux 9.3.0 64bit
	Debian GNU/Linux 9.0.0 64bit
	Debian GNU/Linux 8.10.0 64bit
	Debian GNU/Linux 8.8.0 64bit
	Debian GNU/Linux 8.7.0 64bit
	Debian GNU/Linux 8.6.0 64bit
	Debian GNU/Linux 8.5.0 64bit
	Debian GNU/Linux 8.4.0 64bit
	Debian GNU/Linux 8.2.0 64bit
	Debian GNU/Linux 8.1.0 64bit

OS Type	OS Version (_os_version)	
Fedora	Fedora 30 64bit	
	Fedora 29 64bit	
	Fedora 28 64bit	
	Fedora 27 64bit	
	Fedora 26 64bit	
	Fedora 25 64bit	
	Fedora 24 64bit	
	Fedora 23 64bit	
	Fedora 22 64bit	
EulerOS	EulerOS 2.9 64bit	
	EulerOS 2.5 64bit	
	EulerOS 2.3 64bit	
	EulerOS 2.2 64bit	
	EulerOS 2.1 64bit	
openEuler	openEuler 20.03 64bit	
NeoKylin	NeoKylin 7.4 64bit	
	NeoKylin Server release 5.0 U2 64bit	
	NeoKylin Linux Advanced Server release 7.0 U5 64bit	

## \_\_support\_xen\_gpu\_type Values

Table 9-2 Supported GPU types

Supported GPU (_support_xen_gpu_type)	Description
M60_vGPU	The image has a hardware virtualization drive with the M60 video card installed and supports <b>g1.xlarge</b> and <b>g1.2xlarge</b> ECSs.

## \_\_support\_kvm\_gpu\_type Values

Table 9-3 Supported GPU types

Supported GPU (_support_kvm_gpu_typ e)	Description
M60	The image has a hardware virtualization drive with the M60 video card installed and supports <b>g1.xlarge</b> , <b>g1.2xlarge</b> , and <b>g3.4xlarge.4</b> ECSs.
V100_vGPU	The image has a hardware virtualization drive with the V100 video card installed and supports <b>g5.8xlarge.4</b> ECSs.
P2V_V100	The image has a hardware virtualization drive with the V100 video card installed and supports <b>p2v. 2xlarge.8</b> ECSs.
P100	The image has a hardware virtualization drive with the P100 video card installed and supports p1.2xlarge.8 and p1.4xlarge.8 ECSs.
V100	The image has a hardware virtualization drive with the V100 video card installed and supports p2.2xlarge.8 and p2.4xlarge.8 ECSs.

## **Special Images and Supported OSs**

**Table 9-4** Special image types and supported OSs

Image Type	Supported OS
Large-memory	CentOS 6.6 64bit
	CentOS 6.7 64bit
	CentOS 6.8 64bit
	CentOS 7.1 64bit
	CentOS 7.2 64bit
	CentOS 7.3 64bit
	SUSE Enterprise Linux Server 11 SP3 64bit
	SUSE Enterprise Linux Server 11 SP4 64bit
	SUSE Enterprise Linux Server 12 SP1 64bit
	SUSE Enterprise Linux Server 12 SP2 64bit
	Red Hat Linux Enterprise 6.8 64bit
	Red Hat Linux Enterprise 7.3 64bit
GPU-accelerated (G1)	Windows Server 2008 R2 Enterprise SP1 64bit
	Windows Server 2012 R2 Standard 64bit
	Windows Server 2016 Datacenter
GPU-accelerated (G2)	Windows Server 2008 R2 Enterprise SP1 64bit
	Windows Server 2012 R2 Standard 64bit
Disk-intensive	CentOS 7.2 64bit
	CentOS 7.3 64bit
	CentOS 6.8 64bit
	SUSE Enterprise Linux Server 11 SP3 64bit
	SUSE Enterprise Linux Server 11 SP4 64bit
	SUSE Enterprise Linux Server 12 SP1 64bit
	SUSE Enterprise Linux Server 12 SP2 64bit
	Red Hat Linux Enterprise 6.8 64bit
	Red Hat Linux Enterprise 7.3 64bit

Image Type	Supported OS
High-performance	CentOS 6.8 64bit
	CentOS 7.2 64bit
	CentOS 7.3 64bit
	Windows Server 2008
	Windows Server 2012
	Windows Server 2016
	SUSE Enterprise Linux Server 11 SP3 64bit
	SUSE Enterprise Linux Server 11 SP4 64bit
	SUSE Enterprise Linux Server 12 SP1 64bit
	SUSE Enterprise Linux Server 12 SP2 64bit
	Red Hat Linux Enterprise 6.8 64bit
	Red Hat Linux Enterprise 7.3 64bit



#### Normal

Returned Value	Description
200 OK	The results of GET and PUT operations are returned as expected.
201 Created	The results of the POST operation are returned as expected.
202 Accepted	The request has been accepted for processing.
204 No Content	The results of the DELETE operation are returned as expected.

#### Abnormal

Returned Value	Description
400 Bad Request	The server failed to process the request.
401 Unauthorized	You must enter a username and password to access the requested page.
403 Forbidden	You are forbidden to access the requested page.
404 Not Found	The server cannot find the requested page.
405 Method Not Allowed	You are not allowed to use the method specified in the request.
406 Not Acceptable	The response generated by the server cannot be accepted by the client.
407 Proxy Authentication Required	You must use the proxy server for authentication so that the request can be processed.

Returned Value	Description
408 Request Timeout	The request timed out.
409 Conflict	The request could not be processed due to a conflict.
500 Internal Server Error	Failed to complete the request because of a service error.
501 Not Implemented	Failed to complete the request because the server does not support the requested function.
502 Bad Gateway	Failed to complete the request because the request is invalid.
503 Service Unavailable	Failed to complete the request. The service is unavailable.
504 Gateway Timeout	A gateway timeout error occurred.

## B Error Codes

## **Function Description**

If the returned status code is **400**, a customized error message will be returned. This section describes the meaning of each status code.

#### **Response Format**

```
STATUS CODE 400

{
    "error": {
        "message": "The imagetype is invalid.",
        "code": "IMG.0024"
    }
}
```

## **Error Message Description**

Table B-1 Error codes

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0001	The request message format is invalid.	The request message format is invalid.	Use the correct format.
400	IMG. 0002	The image name contains more than 128 characters.	The image name contains more than 128 characters.	Reduce the length of the image name.
400	IMG. 0003	The image name format is invalid.	The image name format is invalid.	Check whether the image name is valid.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0004	The description contains more than 1024 characters.	The image name contains more than 1024 characters.	Reduce the length of the image description to within 1024 characters.
400	IMG. 0005	The ECS does not exist.	The ECS does not exist.	Check whether the ECS exists.
400	IMG. 0006	The ECS system disk cannot be used to create an image.	The system disk of the ECS cannot be used to create an image.	Check the system disk status of the ECS.
400	IMG. 0007	The request body is empty.	The message body is empty.	Check whether the message body is valid.
400	IMG. 0008	The ECS cannot be used to create images because it is not in stopped state.	The ECS cannot be used to create an image because it is not in the <b>Stopped</b> state.	Stop the ECS and try again.
400	IMG. 0009	The image name already exists.	The image name already exists.	Change another image name.
400	IMG. 0010	The ECS cannot be used to create an image because it has in-progress tasks.	The ECS cannot be used to create an image because it has in-progress tasks.	Try again after the tasks are complete.
400	IMG. 0011	<b>forceCreate</b> must be set to <b>true</b> .	forceCreate must be set to true.	Set <b>forceCreate</b> to <b>true</b> .
400	IMG. 0012	The ECS ID is not specified.	The ECS ID is invalid.	Enter a valid ECS ID.
400	IMG. 0013	The image name is not specified.	The image name is not specified.	Enter a valid image name.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0014	An exception occurred when laaS OpenStack was executing the task.	An exception occurred when laaS OpenStack was executing the task.	Contact technical support.
400	IMG. 0015	The number of private images has reached the maximum allowed.	The number of private images has reached the quota.	Increase the quota or delete existing images.
400	IMG. 0016	An error occurred when the request body was deleted.	An error occurred when the request body was deleted.	Contact technical support.
400	IMG. 0017	The URL format is incorrect.	The URL format is incorrect.	Check whether the URL format is valid.
400	IMG. 0018	An error occurred when the job was submitted.	An error occurred when the job was submitted.	Contact technical support.
400	IMG. 0019	The backup ID is not specified.	The backup ID is not specified.	Check whether the current backup ID is valid.
400	IMG. 0020	The backup does not exist.	The backup does not exist.	Check whether the backup file exists.
400	IMG. 0021	The resource type is unknown.	The source type is unknown.	Select a correct source type.
400	IMG. 0022	The disk in the current state cannot be used to create images.	A disk in the current state cannot be used to create images.	Check the disk status.
400	IMG. 0023	An exception occurred during task query.	An exception occurred during job query.	Contact technical support.
400	IMG. 0024	The image type in the request is incorrect.	The image type in the request is incorrect.	Select either BMS or ECS.
400	IMG. 0025	The user type in the request is incorrect.	The user type in the request is incorrect.	Check whether the user type is valid.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0026	The role is invalid. You need to apply for the required permissions or pass the real-name authentication.	You do not have the rights to perform the operation.	Contact technical support.
400	IMG. 0027	The image ID in the request does not exist.	The image ID in the request does not exist.	Use a valid image ID.
400	IMG. 0028	The image in the request is protected.	The image in the request is protected.	Contact technical support.
400	IMG. 0029	The backup in the request has already been used to create an image.	The backup in the request has already been used to create an image.	Select another backup that has not been used.
400	IMG. 0030	The project ID and token in the request are invalid.	The project ID and token in the request are invalid.	Enter a correct project ID and token.
400	IMG. 0031	The resource ID in the request is incorrect.	The resource ID in the request is incorrect.	Use a valid image ID.
400	IMG. 0032	The backup is unavailable.	The backup is unavailable.	Check whether the backup is available.
400	IMG. 0033	The backup is not a system disk backup.	The backup is not a system disk backup.	Check whether the backup is a system disk backup.
400	IMG. 0034	The number of images cannot be modified.	The number of images cannot be modified.	Contact technical support.
400	IMG. 0035	An attribute conflict occurred during the modification.	An attribute conflict occurred during the modification.	Contact technical support.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0036	An error occurred when the value of asumeToken was obtained.	An error occurred when the value of asumeToken was obtained.	Contact technical support.
400	IMG. 0037	An error occurred in the AK/SK was obtained.	An error occurred in the AK/SK was obtained.	Contact technical support.
400	IMG. 0038	An error occurred when the bucket was created.	An error occurred when the bucket was created.	Contact technical support.
400	IMG. 0039	An error occurred when read and write permissions of the bucket were granted to a specified user.	An error occurred when read and write permissions of the bucket were granted to a specified user.	Contact technical support.
400	IMG. 0040	An error occurred in the object storage address was obtained.	An error occurred in the object storage address was obtained.	Contact technical support.
400	IMG. 0041	The authorized account is empty.	The authorized account is empty.	Use a valid account.
400	IMG. 0045	Failed to generate the image product code.	Failed to generate the image product code.	Contact technical support.
400	IMG. 0046	The image is unavailable.	The image is unavailable.	Check the image status.
400	IMG. 0047	This operation can be performed only by the image owner.	This operation can be performed only by the image owner.	Check whether you have the permission to operate the image.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0053	An error occurred when the domain information of the shadow account was obtained.	An error occurred when the domain information of the shadow account was obtained.	Contact technical support.
400	IMG. 0054	The image description format is invalid.	The image description format is invalid.	Check the image description. It can contain no more than 1024 characters that consist of only letters and digits. Spaces and angle brackets (< >) are not allowed.
400	IMG. 0055	The memory or disk size is invalid.	The memory or disk size is invalid.	Check the memory (MB) or disk size (GB) supported by the image.
400	IMG. 0056	The OS type is invalid.	The OS type is invalid.	Select Windows or Linux.
400	IMG. 0057	The image file does not exist, is empty, or in the incorrect format.	The image file does not exist, is empty, or in the incorrect format.	Select a valid image file.
400	IMG. 0058	The region of the bucket where the image file is stored is inconsistent with that of the user.	The region of the bucket where the image file is stored is inconsistent with that of the user.	Ensure that the bucket where the image is stored is in region as the user.
400	IMG. 0059	The size of the image file exceeds the maximum allowed.	The size of the image file exceeds the maximum allowed.	Check whether the size of the image file is less than or equal to 128 GB.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0060	The number of tasks exceeds the flow control limit.	The number of tasks exceeds the flow control limit.	Wait for a while and then try again.
400	IMG. 0061	Unknown system error.	Unknown system error.	Contact technical support.
400	IMG. 0062	The image name is incorrect.	The image name is incorrect.	Check whether the image name is valid.
400	IMG. 0063	The VM type does not support image creation.	The ECS type does not support image creation.	Select an ECS that supports image creation.
400	IMG. 0064	Failed to obtain tenant information from IAM.	Failed to obtain tenant information from IAM.	Contact technical support.
400	IMG. 0065	Failed to obtain the tenant domain from IAM.	Failed to obtain the tenant domain from IAM.	Contact technical support.
400	IMG. 0066	The image ID is incorrect.	The image ID is incorrect.	Enter a correct image ID.
400	IMG. 0067	The project ID is incorrect.	The project ID is incorrect.	Enter a correct project ID.
400	IMG. 0068	The specified bucket name is empty.	The specified bucket name is empty.	Check whether the specified bucket name is empty and enter a correct bucket name.
400	IMG. 0069	The specified bucket cannot be accessed.	The specified bucket cannot be accessed.	Contact technical support.
400	IMG. 0070	The image file already exists. Confirm the file in the corresponding directory of the OBS bucket or in the OBS bucket.	The image file already exists.	Check whether the file exists in the corresponding directory of the OBS bucket or in the OBS bucket.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0071	The image cannot be exported.	The image cannot be exported.	Select another image.
400	IMG. 0072	The specified image format is not supported.	The specified image format is not supported.	Check the image format. Only VHD, RAW, ZVHD, and QCOW2 are supported. The default format is VHD.
400	IMG. 0073	The name of the exported file is empty.	The name of the exported file is empty.	Enter a correct file name.
400	IMG. 0074	The file name length exceeds the limit.	The file name length exceeds the limit.	Reduce the length of the file name.
400	IMG. 0075	The file name contains invalid characters.	The file name contains invalid characters.	Ensure that the image file name meets the following requirements:  The name cannot start or end with space.  The name contains 1 to 128 characters.  The name contains the following four types of characters:  Uppercase letters  Lowercase letters  Digits  Special characters, including hyphens (-), periods (.), underscores (_), and space

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0076	You cannot share an image with yourself.	You cannot share an image with yourself.	Do not share images with yourself.
400	IMG. 0077	The public image cannot be exported.	The public image cannot be exported.	Select another image.
400	IMG. 0079	The system disk image created from a charged image cannot be exported.	A system disk image created from a charged image cannot be exported.	Select another image.
400	IMG. 0080	The image created from a CBR backup cannot be exported.	The image created from a CSBS backup cannot be exported.	Export the image after the backup is created.
400	IMG. 0081	The image cannot be exported because it is created from an image file.	The image cannot be exported because it is created from an image file.	Select another image.
400	IMG. 0083	The image is a public image.	The image is a public image.	-
400	IMG. 0084	The image is a private image.	The image is a private image.	-
400	IMG. 0085	The publishing mode is incorrect.	The publishing mode is incorrect.	-
400	IMG. 0086	No image was found.	No image was found.	Check whether the image exists.
400	IMG. 0087	The token is incorrect.	The token is incorrect.	Enter a correct token.
400	IMG. 0088	The number of shared images has reached the maximum allowed.	The number of shared images has reached the quota.	Increase the quota.
400	IMG. 0090	The image being created cannot be deleted.	An image being created cannot be deleted.	Delete the image after the image is created.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0092	The image can only be deleted by the owner.	The image can only be deleted by the owner.	Ask the image owner to delete the image.
400	IMG. 0094	The public image cannot be deleted.	The public image cannot be deleted.	Do not delete public images.
400	IMG. 0095	The KMS key does not exist.	The key does not exist.	Check whether the key exists.
400	IMG. 0096	The specified KMS key ID must be different from the image key ID.	The specified KMS key ID must be different from the image key ID.	Check whether the specified KMS key ID is the same as the image key ID.
400	IMG. 0097	The key is not enabled.	The key is not enabled.	Enable the key.
400	IMG. 0099	You do not have the permission to access the key.	You do not have the permission to access the key.	Check whether you have the permission to access the key.
400	IMG. 0100	You do not have OBT permission for KMS.	You do not have OBT permission for KMS.	Check whether you have the OBT permission for KMS.
400	IMG. 0101	The original key does not exist.	The original key does not exist.	Check whether the key is valid.
400	IMG. 0102	The original key is not enabled.	The original key is not enabled.	Enable the original key.
400	IMG. 0103	You do not have the permission to access the original key.	You do not have the permission to access the original key.	Check whether you have the permission to access the key.
400	IMG. 0104	Enter the project name if there are multiple projects in the same region.	Enter the project name if there are multiple projects in the same region.	Enter the project name.
400	IMG. 0105	The operation is not supported.	The operation is not supported.	Contact technical support.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0106	The image owner is another tenant.	The image owner is another tenant.	Confirm the image owner.
400	IMG. 0108	The tenant ID was not found in the current region.	The tenant ID was not found in the current region.	Contact technical support.
400	IMG. 0109	The bucket name contains invalid characters.	The bucket name contains invalid characters.	Check whether the bucket name is valid.
400	IMG. 0110	The system disk is unavailable and cannot be used to create images.	The system disk is unavailable and cannot be used to create images.	Create an image when the system disk is available.
400	IMG. 0111	The size of the system disk exceeds the maximum allowed.	The size of the system disk exceeds the maximum allowed.	Ensure that the ECS system disk size is greater than or equal to the system disk size of the image and smaller than 1024 GB.
400	IMG. 0112	Failed to add the tenant.	Failed to add the tenant.	Contact technical support.
400	IMG. 0113	Failed to delete the tenant.	Failed to delete the tenant.	Contact technical support.
400	IMG. 0114	Failed to query the tenant details.	Failed to query the tenant details.	Contact technical support.
400	IMG. 0115	The image tag is invalid.	The image tag is invalid.	Check the validity of the image tag.
400	IMG. 0116	The number of image tags exceeds the quota.	The number of image tags exceeds the quota.	Delete tags that are unnecessary or not in use.
400	IMG. 0117	The image source can only be BMS or ECS.	The image type can only be BMS or ECS.	Select a BMS or ECS as the image source.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0118	The BMS image does not support KMS encryption.	The BMS image does not support KMS encryption.	Modify the BMS image configuration.
400	IMG. 0119	The VM does not have a system disk.	The ECS does not have a system disk.	Attach a system disk to the ECS.
400	IMG. 0120	The specified data disk ID is unavailable.	The specified data disk ID is unavailable.	Check whether the current data disk ID is valid.
400	IMG. 0121	The object cannot be found.	The object cannot be found.	Check whether the object exists.
400	IMG. 0122	The OS type is invalid.	The OS type is invalid.	Select an OS supported by IMS.
400	IMG. 0123	The image file address in the request is duplicate.	The image file address in the request is duplicate.	Delete the duplicate image file address.
400	IMG. 0125	The data disk image cannot be converted to a public image.	The data disk image cannot be published as a public image.	Check the constraints on data disk images.
400	IMG. 0126	The VM in the current stage cannot be used to create a full-ECS image.	The ECS in the current status cannot be used to create a full-ECS image.	Check the ECS status. Ensure that the ECS is in the Running or Stopped state.
400	IMG. 0128	The full-ECS image cannot be exported.	A full-ECS image cannot be exported.	Check the constraints on image export.
400	IMG. 0130	The full-ECS image cannot be exported or replicated.	A full-ECS image cannot be exported or replicated.	Check the constraints on full-ECS images.
400	IMG. 0135	The full-ECS image cannot be shared.	A full-ECS image cannot be shared.	Check the constraints of image sharing.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0136	Failed to create a full-ECS image because the ECS is being backed up.	Failed to create a full-ECS image because a backup is being created for the ECS.	Wait until the CBR backup becomes available.
400	IMG. 0137	Failed to obtain the VM information.	Failed to obtain the ECS information.	Check whether the ECS ID is correct and whether you have the permission to perform operations on the ECS.
400	IMG. 0138	Failed to obtain the OS type information.	Failed to obtain the OS type information.	Contact technical support.
400	IMG. 0139	Other disks on the VM are being used to created VMs.	Other disks on the ECS are being used to create ECSs.	Contact technical support.
400	IMG. 0140	The disks in the request come from different ECSs.	The disks in the request are from different ECSs.	Ensure that the ECS to which the disks are attached is the same.
400	IMG. 0141	The value of hw_firmware_type is not uefi or bios.	The value of hw_firmware_t ype is not uefi or bios.	Set hw_firmware_type to uefi or bios.
400	IMG. 0142	Replication must be performed across regions.	Replication must be performed across regions.	Select another destination region.
400	IMG. 0143	An encrypted image cannot be replicated cross regions.	An encrypted image cannot be replicated cross regions.	Select an unencrypted image.
400	IMG. 0144	The image does not exist.	The image does not exist.	Check whether the image exists.
400	IMG. 0145	The project name is incorrect.	The project name is incorrect.	Enter a correct project name.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0146	The size of the image to be replicated across regions exceeds the upper limit.	The size of the image to be replicated across regions exceeds the upper limit.	Check whether the image size is less than or equal to 128 GB.
400	IMG. 0147	The entered region information is incorrect.	The entered region information is incorrect.	Enter the correct region information.
400	IMG. 0148	The image is being exported.	The image is being exported.	Wait until the image is exported.
400	IMG. 0149	The number of image replicated cross regions exceeds the maximum number allowed at a time.	The number of images replicated cross regions exceeds the maximum number allowed at a time.	Try again later.
400	IMG. 0150	The CSBS backup used to create the full-ECS image already exists in the destination region and cannot be used again.	The CSBS backup used to create the full-ECS image already exists in the destination region, and the full-ECS image cannot be replicated again.	Do not copy the full-ECS again.
400	IMG. 0151	The agency does not have the needed permissions to perform this operation on the target project.	The agency does not have the permissions to perform this operation on the target project.	Create an agency again. The agency must have the IMS Administrator permission in both the source and destination regions.
400	IMG. 0152	The full-ECS image is available only in the specified AZ.	A full-ECS image is available only in the specified AZ.	Contact technical support.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0153	DESS or DSS disks cannot be used to create images.	DESS or DSS disks cannot be used to create images.	Select another ECS.
400	IMG. 0154	Failed to communicate with Enterprise Project Management Service (EPS).	Failed to communicate with EPS.	Contact technical support.
400	IMG. 0157	Incorrect image type.	Incorrect image type.	Select a correct image type.
400	IMG. 0158	Only image files in raw OR ZVHD2 format support the Fast Create function. For raw image files, bitmaps must be uploaded to the OBS bucket together with image files.	Only image files in RAW or ZVHD2 format support the fast image creation function. For RAW image files, bitmap files must be uploaded to the OBS bucket together with image files.	Check the image file format. If a RAW image file is used, provide the bitmap file.
400	IMG. 0159	The OS version is required when image files are used to create ECSs through the fast image creation function.	os_version is required when image files are used to create ECSs through the fast image creation function.	Enter the OS version.
400	IMG. 0160	Only images less than 128 GB can be exported.	Only images smaller than 128 GB can be exported.	Images larger than 128 GB cannot be exported.
400	IMG. 0161	You do not have permission.	No OBT permissions for displaying the vendor name.	Contact technical support.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0162	The value contains a maximum of 12 characters that consist of letters and spaces, and cannot start or end with a space	The value contains a maximum of 12 characters that consist of letters and spaces, and cannot start or end with a space.	Check whether the vendor name is valid.
400	IMG. 0163	This image cannot be titled by vendors. Only images running a Windows OS booted in BIOS mode can be titled by vendors.	This image cannot be titled by vendors.	Contact technical support.
400	IMG. 0164	Failed to create an image because the spot ECS is being reclaimed.	Failed to create an image because the spot ECS is being reclaimed.	Failed to create an image because the spot ECS is being reclaimed.
400	IMG. 0166	OS information must be contained in the ISO files used to create images.	OS version information must be contained when an ISO file is used to create an image.	OS version information must be contained when an ISO file is used to create an image.
400	IMG. 0167	This operation cannot be performed for ISO images.	The ISO image does not support this function.	Contact technical support.
400	IMG. 0168	Data disk images cannot be updated.	Data disk images cannot be updated.	Contact technical support.
400	IMG. 0169	Failed to update the image because the OS versions are different.	Failed to update the image because the OS versions are different.	Contact technical support.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0170	Failed to update the image because the image formats are different.	Failed to update the image because the image formats are different.	Contact technical support.
400	IMG. 0171	Failed to update the image because the minimum disk space is less than that of the source image.	Failed to update the image because the minimum disk space is less than that of the source image.	Contact technical support.
400	IMG. 0172	Failed to update the image because the minimum memory is less than that of the source image.	Failed to update the image because the minimum memory is less than that of the source image.	Contact technical support.
400	IMG. 0173	Failed to update the image because the image environment types are different.	Failed to update the image because the image environment types are different.	Contact technical support.
400	IMG. 0174	Failed to update the image because the name of the source image is different from that of the target image.	Failed to update the image because the name of the source image is different from that of the target image.	Contact technical support.
400	IMG. 0175	The folder name and image file name cannot contain spaces.	The folder name and image file name cannot contain spaces.	Check whether the file name is valid.
400	IMG. 0176	Failed to delete the full-ECS backup.	Failed to delete the full-ECS backup.	Contact technical support.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0177	The source and target tenants reside in different regions.	The source and target tenants reside in different regions.	Check whether the source and target tenants reside in the same region.
400	IMG. 0178	The target tenant is the same as the source tenant.	The target tenant is the same as the source tenant.	The target tenant cannot be the same as the source tenant. Please check.
400	IMG. 0179	The token of the source image agency is invalid.	The token of the source image agency is invalid.	Contact technical support.
400	IMG. 0180	CBR does not support full-ECS image creation.	CBR does not support full-ECS image creation.	Contact technical support.
400	IMG. 0181	Failed to obtain ECSs that can be protected.	Failed to obtain ECSs that can be protected.	Contact technical support.
400	IMG. 0182	Insufficient vault capacity. Please expand the capacity.	Insufficient vault capacity. Please expand the capacity.	Check whether the vault capacity is sufficient.
400	IMG. 0183	The ECS can only be associated with one vault.	The ECS can only be associated with one vault.	Ensure that the resource is not associated with any other vault.
400	IMG. 0184	Failed to obtain the vault.	Failed to obtain the vault.	Check whether the vault exists.
400	IMG. 0185	The number of ECSs associated with the vault has reached the upper limit.	The number of ECSs associated with the vault has reached the upper limit.	Create another vault or delete unused resources.
400	IMG. 0187	KMS access traffic has reached the upper limit.	KMS access traffic has reached the upper limit.	Contact technical support.
400	IMG. 0188	Vault is unavailable.	Vault is unavailable.	Contact technical support.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0189	The target CBR vault does not support image replication.	The target CSBS vault does not support image replication.	Contact technical support.
400	IMG. 0190	Full-ECS images can be created only from CBR backups.	Full-ECS images can be created only from CBR backups.	Contact technical support.
400	IMG. 0191	Failed to query ECS flavors.	Failed to query ECS flavors.	Contact technical support.
400	IMG. 0192	The flavor used to query images is invalid.	The flavor used to query images is invalid.	Contact technical support.
400	IMG. 0193	The vault is not a cloud server backup vault.	The vault is not a CBR backup vault.	Check that the vault is a CBR backup vault.
400	IMG. 0194	The maximum number of images that can be imported at one time has been reached.	The maximum number of images that can be imported at one time has been reached.	Contact technical support.
400	IMG. 0195	Full-ECS images created from CBR backups must contain an OS.	Full-ECS images created from CBR backups must contain the OS version.	Specify the OS version.
400	IMG. 0196	The image cannot be replicated because it is not accepted by the recipient.	The image cannot be replicated because it is not accepted by the recipient.	Accept the shared image.
400	IMG. 0197	Failed to replicate the shared image because it is encrypted using KMS.	Failed to replicate the shared image because it is encrypted using KMS.	Shared encrypted images cannot be replicated.

Statu s Code	Error Code	Message	Description	Handling Measure
400	IMG. 0198	Backup ID does not match the backup type or does not exist.	Backup ID does not match the backup type or the backup does not exist.	Check whether the backup ID matches the backup type.
400	IMG. 0212	The value of architecture is not x86 or arm.	The value of architecture is not x86 or arm.	Set <b>architecture</b> to <b>x86</b> or <b>arm</b> .
400	IMG. 0238	Not real-name authentication.	Real-name authentication is not performed.	Perform real-name authentication.
400	IMG. 0239	Insufficient balance.	The account balance is insufficient.	Check the balance and top up the account if needed.
400	IMG. 0241	Incomplete payment information.	The payment information is incomplete.	Complete the payment information.
400	IMG. 0242	Insufficient budget of enterprise department.	The department budget is insufficient.	Increase the budget.
400	IMG. 1075	Failed to register the image file.	Failed to register the image file.	Contact technical support.

# C Change History

Released On	Description
2023-02-13	This issue is the seventh official release.
	Modified the following content:
	<ul> <li>Deleted is_config_init from the example request in Creating an Image.</li> </ul>
	<ul> <li>Added the sub_jobs_result and sub_jobs_list response parameters in Asynchronous Job Query.</li> </ul>
	<ul> <li>Modified disk_format description in Querying Images, Querying Images (Native OpenStack API), Querying Image Details (Native OpenStack API), and Image Attributes.</li> </ul>
	<ul> <li>Added error codes IMG.0161, IMG.0162, IMG.0163, IMG.0164, IMG.0212, IMG.0238, IMG.0239, IMG.0241, IMG.0242, and IMG.1075 in Error Codes.</li> </ul>
	<ul> <li>Added the response parameter properties in Creating Image Metadata (Native OpenStack API).</li> </ul>
	<ul> <li>Added details about the values hss and ces as well as constraints on hss in Updating Image Information (Native OpenStack API).</li> </ul>
	<ul> <li>Changed the return value indicating a normal state to 300 in Querying API Versions (Native OpenStack API) and Querying an API Version (Native OpenStack API).</li> </ul>
	<ul> <li>Changed Redhat to Red Hat in Querying Images, Updating Image Information, Creating an Image, Querying Images (Native OpenStack API), Querying Image Details (Native OpenStack API), and Updating Image Information (Native OpenStack API).</li> </ul>

Released On	Description
2021-11-15	This issue is the sixth official release.  Modified the following content:  Optimized the description for creating an image in Creating an Image.
2021-07-31	This issue is the fifth official release.  Added the following content:  Introduction
2021-06-30	This issue is the fourth official release.  Modified the following content:  • Added the methods of querying OBS bucket names and OBS bucket object names in the description of the image_url parameter in Creating an Image.
2021-04-15	This issue is the third official release.  • Added image encryption.
2021-01-18	This issue is the second official release. Added the following content: Examples
2020-02-26	This issue is the first official release.